

Easy WP Guide

WordPress Manual

anthony hortin
maddisondesigns

Easy WP Guide WordPress Manual

by Anthony Hortin

Maddison Designs

maddisondesigns.com

Copyright © 2014 Anthony Hortin

All rights reserved

Published December 2014

Version: 3.1 for WordPress 4.1

ISBN: 978-0-9872955-7-6

easywpguide.com

Contents

Welcome	7
Introduction	8
Login	10
Dashboard	11
Dashboard Menu Options	12
Toolbar	14
Hiding the Toolbar	15
Posts versus Pages	16
Posts	16
Pages	18
Adding your Site Content	21
Adding a New Page	21
Adding a New Post	22
Adding Content with the Visual Editor	24
Switching to the Text Editor	27
Changing your Post Format	30
Reviewing Past Revisions	31
Adding Images and Other Media	33
Inserting an Image	33
Edit or Delete an Image	39
Setting a Featured Image	43
Insert an Image Gallery	44

Edit or Delete an Image Gallery.....	46
Insert an Audio or Video Playlist.....	47
Inserting Video, Audio or Other File Type	50
Embedding a Video, Image or Other Content	51
Adding HTML Links	55
Inserting an HTML Link.....	55
Inserting Links to Media Files	56
Editing an HTML Link.....	58
Removing an HTML Link	58
Editing Existing Content.....	59
Deleting Content	60
Fullscreen Editing	62
Saving and Publishing Content	63
Categories	65
Adding Categories within your Post	68
Tags	69
Adding Tags within your Post	71
Media Library.....	73
Viewing a File in the Media Library.....	75
Adding a File to the Media Library	76
Editing the File Properties	78
Editing an Image	80
Deleting a File from the Media Library	84
Comments	85

Replying to a Comment	86
Editing a Comment	89
Quick edit	89
Edit	89
Unapproving and Approving Comments.....	90
Marking Comments as Spam and Trash	91
Appearance.....	94
Selecting your Theme.....	94
Previewing and Customizing your Theme.....	95
Adding a new Theme	96
Customizing your Site	97
Widgets	98
Updating the Menu	101
Adding a New Menu	103
Editing an Existing Menu Item.....	103
Adding a New Menu Item.....	105
Adding a Custom Link Menu Item	106
Deleting a Menu Item	107
Managing Menu Locations.....	107
Header	108
Background.....	109
Editor	110
Plugins	111
Adding a New Plugin	112
Users.....	116

Adding a New User	117
Deleting a User.....	119
Editing your Profile	120
Tools	124
Press This	124
Categories and Tags Converter	124
Import	124
Export.....	124
Settings.....	126
General.....	126
Writing.....	127
Reading	128
Discussion	129
Media	132
Permalinks.....	132
Keeping your Site Updated.....	134
Where To From Here?	137

Welcome

It might be easier to say what this guide isn't, rather than what it is. It isn't an in depth look at every single function available within the WordPress dashboard. Nor is it a guide to help you develop or modify WordPress themes. My aim is to create a simple WordPress guide that will help you to get an overall understanding of how you use the various features within the WordPress Dashboard to keep your site or blog updated.

If you're looking for more in-depth knowledge, there are heaps of articles in the [WordPress Codex](#) that go into more detail. This is great if you want to get really involved in developing your own WordPress theme or modifying your site with plugins, but it can be a bit daunting for those users who just want a simple guide to using the Content Management side of WordPress or just need to update their site pages every so often.

Introduction

WordPress is an [Open Source](#) software system used by millions of people around the world to create beautiful websites and blogs. It is completely customisable by the use of [themes](#) and [plugins](#).

“WordPress is web software you can use to create a beautiful website or blog. We like to say that WordPress is both free and priceless at the same time.”

Themes can be easily downloaded from the official WordPress site or from hundreds of other places around the web. The same goes with plugins, which are used to extend the functionality of your WordPress site.

As well as being a fantastic blogging and content management system, one of the huge benefits is the wealth of information out there. There’s a great community of people behind the design & development of the WordPress system itself. People from all over the world contribute their time, knowledge and skill to keeping WordPress updated and secure.

There’s also a huge number of designers, developers & bloggers who share their knowledge through blog posts, tutorials, reviews, videos and the creation of thousands of themes & plugins.

WordPress powers a staggering amount of websites. In fact, it powers over 23% of the whole web! Everything from personal blogs to large corporate websites. The following are just a very few examples of the millions of diverse sites powered by WordPress...

Vogue – <http://www.vogue.com>

Vogue is a globally recognised fashion and lifestyle magazine, published monthly by Condé Nast.

The New Yorker – <http://www.newyorker.com>

The New Yorker is an American magazine of reportage, commentary, criticism, essays, fiction, satire, cartoons, and poetry, published by Condé Nast.

Sweden's Official Site – <http://sweden.se>

The website is the official source for facts about Sweden. It is publicly funded, with four organisations behind it: the Swedish Institute; the Swedish Government Offices, including the Ministry for Foreign Affairs and the Ministry of Enterprise, Energy and Communications; Business Sweden; and VisitSweden.

Felicia Day – <http://feliciday.com>

Felicia Day is a professional actress who has been in numerous movies, tv shows and commercials. She also created “The Guild”, an independent web series with over 6 million hits web-wide. Her passions include video games, fantasy novels, web 2.0, wordpress, cooking, playing with her cats and making people laugh.

The Official Star Wars Blog – <http://www.starwars.com/news>

Star Wars is an American epic space opera franchise conceived by George Lucas. The first film in the franchise was originally released on May 25, 1977, by 20th Century Fox, and became a worldwide pop culture phenomenon. Star Wars is one of the most popular movie series of all time and the series' official blog is powered by WordPress.

Aqua Hotels and Resorts – <http://www.aquaresorts.com>


Aqua Hotels & Resorts is a full-service hotel management company founded in 2001 by Hawaii hotelier Michael V. Paulin.

SlashGear – <http://slashgear.com>

SlashGear is a gadget and technology blog that features reviews, columns, videos, photos, discussions, and more. SlashGear receives millions of readers per month and uses WordPress to power its entire site, including main site, bbPress-powered forums, and video site.

Login

Before you can make any changes to your site, you will need to log in. The login for your site is typically found at the following URL - <http://your-wordpress-site.com/wp-admin>. Obviously, replace *your-wordpress-site.com* with your actual domain name.




There are exceptions to this of course. For instance, your WordPress setup may be installed in a subdirectory. For most standard setups though, you'll find the above [URL](#) should work.

Dashboard

Once you've logged in, the WordPress Dashboard appears. This is your main administration homepage. At the very top of your Dashboard (and across every page) you will see the name of your site in the header area. In the example screenshot below (and throughout this documentation) the site name is *Your WordPress Site*. This is also hyperlinked to your site's homepage. You will also see the name of the person who is currently logged in (e.g. Joe Blogg). Move your cursor over your name to reveal the *Log Out* link as well as a link to edit your Profile.

When new or updated features are introduced into WordPress, you'll be shown a *New Feature Pointer*. This is simply to bring to your attention some feature within the Dashboard that's been added or updated. In the following Dashboard image, the New Feature Pointer is highlighting the updated Toolbar. Click *Dismiss* to hide the pointer.




On most pages, just below your Username there are a couple of small inverted tabs. One called *Screen Options* and another called *Help*. Clicking either of these links will cause a panel to slide down from the top of the page. The *Help* link, not surprisingly, displays some help information. The *Screen Options* link will display various options that allow you to configure what is displayed on the current page. The details in this panel change depending on what page you're currently

viewing. As an example, on your main Dashboard page the Screen Options allow you to set which panels you'd like displayed on the page.

Dashboard Menu Options

Down the left-hand side of the Dashboard and on every page you will see your main navigation menu. This is where you'll find all the options to update and configure your site.

Hovering your cursor over each of the main menu options will display a 'fly-out' menu with the various choices for that particular menu option. Once you click each of the main menu options, that particular menu will expand to show all the available options within that section (if there are any).



The main menu options and their usage are:

Dashboard

This will display your main Dashboard 'homepage'. In the top left of your Dashboard you'll see some brief stats on the number of Posts, Pages and Comments. If you have the [Akismet](#) anti-spam plugin activated, you'll also see the number of [Spam Comments](#) or comments awaiting moderation.

Posts

This is where you can create a new Blog Post. You can also update your Categories and Post Tags.

Media

This is where all your uploaded images, documents or files are stored. You can browse through your Media library, as well as edit and update the files.

Pages

This is where you create and maintain all your Pages.

Comments

You can manage all your Comments within this section, including replying to comments or marking them as spam.

Appearance

This menu is where you control how your site looks. You can choose a new Theme, manage your site Widgets or Menus and even edit your site theme files.

Plugins

Plugins extend and expand the functionality of WordPress. You can add or delete plugins within here as well as activate or deactivate them.

Users

This screen lists all the existing users for your site. Depending on your Role, you can also add new users as well as manage their Roles.

Tools

This section gives you access to various convenient tools. You can also import data to your WordPress site or export all your WordPress data to a file.

Settings


This is where most of your site is configured. Among other things, it allows you to configure your site name and URL, where your Posts appear, whether people can leave Post Comments or not and numerous other settings. Most times, once your site is setup, there's no need to change any of the settings within this section.

At the bottom of the menu you'll see a link called *Collapse menu*. Clicking this will hide the menu and simply display their icons instead. Click the small arrow icon again to expand the menu.

Occasionally when you install a plugin, they will have their own configuration or setup pages. The location of these will be entirely dependent on the individual plugin but most times these pages will either appear within the *Tools* section, the *Settings* section or in a completely new menu section at the bottom of the menu.

Toolbar

The WordPress Toolbar is a way of easily accessing some of the most common WordPress features. When you are logged into your WordPress dashboard and you visit your website, you will see the Toolbar running across the top of your site. This bar only appears if you are currently logged into your WordPress site, which means that it won't be visible to your everyday site visitors. If you are not logged in, the Toolbar won't be displayed.



The Toolbar allows you to quickly access the following commonly used features.


- Visit the WordPress.org website, Codex or Support forums
- Display your site Dashboard and other commonly used menu options that allow you to update your site Themes, Widgets, Menus and depending on your theme, Background and Header
- View or Edit your blog comments

- Add a new Post, Media, Page or User
- Edit the current Page or Post
- Perform a site Search

View or Edit your Profile and logout from the WordPress Dashboard

Hiding the Toolbar

You can stop the Toolbar from displaying by modifying the preferences associated with your Profile. Simply click on the *Users* link in the left-hand navigation to display the list of Users. From this list of Users, click your user name or click on the *Edit* link that appears beneath the user name when hovering your cursor over each row. Alternatively, click on the *Your Profile* link underneath the *Users* menu option in the left-hand navigation or within the fly-out menu.



When editing your Profile there is a Toolbar option as shown in the screen above.

- **Show Toolbar when viewing site** – Checking this box will display the Toolbar at the very top of your website (only for the person who is currently logged in)


Posts versus Pages

WordPress is built around two basic concepts. Posts and Pages. Posts are typically blog entries. A series of articles, listed (usually) reverse-chronologically. Pages are used for more static content (i.e. content that doesn't change or changes infrequently). An 'About us' page is an example of a Page on a typical website. In most cases you'll find that the content in the 'About us' page doesn't change all that frequently.

Now, you might be thinking, "but I don't need a blog". This might be true, but you can also use the blog concept if you have a site where you need to display your 'latest news' or even just company updates. Basically, any information that gets updated on a semi-regular basis can benefit from the 'blog' functionality. Whether that's a traditional blog, your company's 'latest news' or even just your own personal updates.

Posts

After clicking on the *Posts* menu option you'll be shown a list of Posts that your site contains. Among the information displayed is the Post title, the Author, Categories, Tags, No. of Comments and either the Date Published, Date Scheduled or the Date the Post was Last Modified. The Posts screen will look similar to the screen below.



At the top of the page you can view how many Posts in total you have in your site, how many are Published, Scheduled, Sticky, Pending, in Draft or in the Trash.



When hovering your cursor over each row, a few links will appear beneath the Post title.

- **Edit** – Will allow you to edit your Post. This is the same as clicking on the Post title
- **Quick Edit** – Allows you to edit basic Post information such as Title, Slug, Date plus a few other options
- **Trash** – Will send the Post to the Trash. Once the Trash is emptied, the page is deleted

- **View** – Displays the Post. If the Post hasn't been published yet, this will say *Preview*


Next to each Post title is a checkbox. This allows you to perform an action on multiple items at once. You simply check the Posts that you would like to affect and then from the Bulk Actions dropdown select either the *Edit* option or the *Move to Trash* option and then click the *Apply* button. The *Edit* option will allow you to edit the Categories, Tags, Author, whether to allow Comments and Pings or not, the Status and whether or not the Posts are 'Sticky'. The *Move to Trash* option will move the selected items to the Trash.

You can also filter the pages that are displayed using the dropdown lists and the *Filter* button.

At the top of the list of Posts there are also two icons that change how the list is displayed. Click the *List View* icon () to display the posts in the traditional List View or click the *Excerpt View* icon () to display a short excerpt from the Post underneath the Post title.

Pages

After clicking on the *Pages* menu option you'll be shown a list of Pages that your site contains. Among the information displayed is the Page title, the Author, No. of Comments and either the Date Published or the Date the Page was Last Modified. The Pages screen will look similar to screen below.



At the top of the page you can view how many Pages in total you have in your site and how many are Published or in Draft.

When hovering your cursor over each row, a few links will appear beneath the Page title.

- **Edit** – Will allow you to edit your Page. This is the same as clicking on the Page title
- **Quick Edit** – Allows you to edit basic Page information such as Title, Slug, Date plus a few other options
- **Trash** – Will send the Page to the Trash. Once the Trash is emptied, the page is deleted

- **View** – Displays the Page. If the Page hasn't been published yet, this will say *Preview*

Next to each Page title is a checkbox. This allows you to perform an action on multiple items at once. You simply check the Pages that you would like to affect and then from the Bulk Actions dropdown select either the *Edit* option or the *Move to Trash* option and then click the *Apply* button. The *Edit* option will allow you to edit the Author, Parent, Template, whether to allow Comments or not and the Status of each of the checked items. The *Move to Trash* option will move the selected items to the Trash.


You can also filter the pages that are displayed using the dropdown list and the *Filter* button.

Adding your Site Content

Adding content to your site is an easy process no matter whether you're creating a Post or a Page. The procedure for both is almost identical. Apart from how they display on your site, which was described earlier, the other main difference is that Posts allow you to associate [Categories](#) and [Tags](#) whereas Pages don't. What's the difference between categories and tags? Normally, Tags are ad-hoc keywords that identify important information in your Post (names, subjects, etc) that may or may not recur in other Posts, while Categories are pre-determined sections. If you think of your site like a book, the Categories are like the Table of Contents and the Tags are like the terms in the index.

Adding a New Page

To add a new Page, hover your cursor over the *Pages* menu option in the left-hand navigation menu and in the fly-out menu, click the *Add New* link. Alternatively, click the *Pages* menu option and then click the *Add New* link underneath, or the *Add New* button at the top of the page. You will be presented with a page similar to the image below.



Adding a New Post

To add a new Post, hover over the *Posts* menu option in the left-hand navigation menu and in the fly-out menu, click the *Add New* link. Alternatively, click the *Posts* menu option and then click the *Add New* link underneath, or the *Add New* button at the top of the page. You will be presented with a page similar to the image below.

WordPress Dashboard: Your WordPress Site | 0 | + New | Howdy, Joe Blogg

Add New Post

Enter title here

Visual | Text

Paragraph | U | A | Ω | ↶ | ↷

Editor Toolbar

Your Post can be styled using the various menu bar buttons. These buttons are also used to add links, upload & insert images, media files & other documents. Using the *Visual* & *Text* tabs, you can switch between the Visual editor or the HTML editor.

Publish Panel

Once your content is added, you can publish your Post or save it as a draft

Editor

This is the Editor where your Post content is added

Word count: 0

Video
 Audio
 Quote
 Link
 Gallery





Categories
 All Categories | Most Used
 aciform
 sub
 antiquarianism
 arrangement
 asmodeus
 Blogroll
 broder
 buying
[+ Add New Category](#)

Tags


Separate tags with commas
[Choose from the most used tags](#)

Featured Image
[Set featured image](#)


Adding Content with the Visual Editor


The editor used to enter content into your Page or Post is very easy to use. It's much like using a regular word processor, with toolbar buttons that allow you to **Bold** () or *Italicize* () text or enter in Headings () or bullet points (). You can even use most of the basic keyboard shortcuts used in other text editors. For example: *Shift+Enter* inserts a line break, *Ctrl+C/Cmd+C* = copy, *Ctrl+X/Cmd+X* = cut, *Ctrl+Z/Cmd+Z* = undo, *Ctrl+Y/Cmd+Y* = redo, *Ctrl+A/Cmd+A* = select all, etc. (use the *Ctrl* key on a PC or the *Command* key on a Mac).

With WordPress 4.0 and above, the Visual Editor now expands to fit your content, rather than simply scrolling. On top of that, no matter how tall the Visual Editor becomes, the toolbar buttons will be available at all times by sticking to the top of the page.

At the top of the editor there are two tabs, *Visual* and *Text* (). These switch the editor view between the *Visual Editor* and the *Text editor*. The Text view will enable you to view the HTML code that makes up your content. For the more experienced users this can be helpful at times but for those not familiar with HTML tags, it's not recommended.

When creating a new Page or Post, the first thing to do is enter in your title in the top entry field where it says *Enter title here*. After moving the cursor down to the editor a new [Permalink](#) is created for your page. Permalinks are the permanent URL's to your individual Posts, Pages, Categories etc.. Though not usually necessary, you can manually edit your permalink by clicking on the actual permalink (the part after the domain name with the yellow background) or by clicking the *Edit* button next to it. Once you've modified it, click *Ok* to save or *Cancel* to cancel your changes.

At the top of the editor where your content is written, there are numerous formatting buttons. Clicking the *Toolbar Toggle* button () will show or hide a second line of formatting buttons which gives you extra functionality. The editor buttons perform the following functions:



Add Media – Used to upload and insert media such as images, audio, video or documents



Bold – Bold text



Italic – Italicise text



Strikethrough – Add a strikethrough to your text



Bulleted List – Create an unordered (bullet point) list



Numbered List – Create an Ordered (numbered) list



Blockquote – Used as a way of showing a quote. How this looks will be entirely dependent on the Theme that your site is currently using



Horizontal Line – Inserts a horizontal line into your page



Align Left – Align text to the left



Align Center – Align text in the center of the page



Align Right – Align text to the right



Insert/edit link – Used to create an html link to another page or website. The text or image that you want to link needs to be selected first before the button will become active



Remove link – Remove the html link from the selected link. Your cursor must be sitting on an active link for the button to be active



Insert Read More tag – Inserts the More tag into your Page. Most blogs only display a small excerpt of a Post and you're required to click the Post title or a 'Read more...' link to continue reading the rest of the article. When you insert a 'More' tag into your Post, everything prior to the tag is considered as this excerpt. Most times you'd only use this button when you're creating a blog Post, rather than a Page



Toolbar Toggle – Used to show or hide the second row of formatting buttons on the editor toolbar



Distraction Free Writing – Clicking this button will enlarge the editor so that it fills the browser window. Clicking the *Exit fullscreen* link at the top of the screen will reduce it back to its original size

Paragraph ▼

Style – Used to format the Page text based on the styles used by the current Theme



Underline – Underline your text



Justify – Align text on both the left and right (i.e. justify)



Text color – Use to change the color of text



Paste as text – Copying and pasting text from other sites or word processors sometimes leaves the text formatted differently to what you were expecting. The reason for this is that quite often the html tags or codes that formatted the original text are pasted along with the text itself. To avoid this, Paste as Text will strip all these formatting and html tags. The Paste as Text option acts like a toggle, staying on until you turn it off by clicking the button again or until you save your page content



Clear formatting – Use this to remove all the formatting (e.g. Bold, Underline, text color etc..) from the highlighted text



Special character – Used to insert special characters not easily accessible via the keyboard (e.g. ¼, ½, ¾, ©, €, ö etc..)



Decrease indent – Removes one level of indenting



Increase indent – Indents text by one level



Undo – Undo your last action



Redo – Redo your last action




Keyboard shortcuts – Displays information about the WordPress Visual Editor along with keyboard shortcuts

Visual


Text

Visual/Text – Switches the editor view between the Visual Editor and the Text editor. The Text view will enable you to view the HTML code that makes up your content. For the more experienced users this can be helpful at times but for those not familiar with HTML tags, it's not recommended

Switching to the Text Editor

At the top of the editor there are two tabs, *Visual* and *Text* (). These switch the editor view between the Visual Editor and the Text editor. The Text view will enable you to view the HTML code that makes up your content. For the more experienced users this can be helpful at times but for those not familiar with HTML tags, it's not recommended.

The Text editor is much like the Visual Editor, only not as intuitive. The numerous formatting buttons provide you with basic HTML formatting capabilities when editing your Page or Post content.



The buttons work in two ways. Clicking a button without highlighting any text first, will simply insert the opening HTML tag relevant for that button. As an example, clicking the *Bold* button will insert the `` HTML tag into your text. Clicking the *Bold* button again will close the tag by inserting the closing `` tag. If you highlight some text prior to clicking a button, both the opening and closing tags will be inserted around that highlighted text. For example, highlighting the text, 'bold text', prior to clicking the *Bold* button will insert '`bold text`'.

The following editor buttons are available whilst in the Text editor:




Bold – Bold text



Italic – Italicise text



Link – Used to insert a website link. When the button is clicked a pop-up window will appear where you type in the URL that you would like to link to



Blockquote – Used as a way of showing a quote. How this looks will be entirely dependent on the Theme that your site is currently using



Delete – Used as a way of showing deleted text. How this looks will be dependent on the Theme but is usually done by showing the text with a strikethrough

ins

Insert – Used as a way of showing inserted text. How this looks will be dependent on the Theme but is usually done by showing the text with an underline

img

Image – Used to insert an image into the text. When the button is clicked a pop-up window will appear where you type in the URL of the image that you would like inserted

ul

Unordered List – Used to insert an unordered (bullet point) list

ol

Ordered List – Used to insert an ordered (numbered) list

li

List Item – Used to insert a list item into your ordered or unordered list

code

Code –Used for indicating a piece of code

more

More – Inserts the More tag into your Page. Most blogs only display a small excerpt of a Post and you're required to click the Post title or a 'Read more...' link to continue reading the rest of the article. When you insert a 'More' tag into your Post, everything prior to the tag is considered as this excerpt. Most times you'd only use this button when you're creating a blog Post, rather than a Page




Distraction Free Writing – Clicking this button will enlarge the editor so that it fills the browser window. Clicking the *Exit fullscreen* link at the top of the screen will reduce it back to its original size

close tags

Close Tags – Used to close open tags. If for example, you clicked both the Bold and Italic buttons to insert their opening tags, clicking the Close tags button will insert both of the matching closing tags, in the correct order

Changing your Post Format

A Post Format is meta information that can be used within a Theme to style or customise the presentation of a Post. The Post Formats feature provides a standardised list of formats that are available to all themes that support the feature. There is no requirement for Themes to support every format on the list and new formats cannot be introduced by themes or even plugins. If your Theme supports Post Formats you can choose how each Post looks by selecting a *Post Format* from a list of radio buttons, similar to the following screen. If your Theme doesn't support Post Formats then the *Format* panel won't be displayed.



While the actual post content entry won't change, the theme can use the selected Format to display the post differently. How content is displayed is entirely up to the Theme, but the following list of available Post Formats provides some general WordPress guidelines as to how they might be styled.


- **Aside** – Typically styled without a title. Similar to a Facebook note update
- **Audio** – An audio file, such as a Podcast
- **Chat** – A chat transcript
- **Gallery** – A gallery of images. Post will likely contain a gallery [shortcode](#) and will have image attachments

- **Image** – A single image
- **Link** – A link to another site
- **Quote** – A quotation, most likely contained within a blockquote
- **Status** – A short status update, similar to a Twitter status update
- **Video** – A single video

Reviewing Past Revisions

When you're editing your Post or Page, the number of revisions for that particular Post or Page is shown in the *Publish* Panel, if you have any.

Click the *Browse* link next to *Revisions*: in the *Publish* panel to browse through the various revisions for the current Post or Page.



Use the slider at the top of the page or click the *Previous* and *Next* buttons to navigate through your various Post or Page revisions.

Content that has been deleted will be shaded red and content that has been added will be shaded green. If there is content that is shaded dark red and/or dark green, it's highlighting specific content that was removed or added. If the paragraph or line is simply light red and/or light green, then the whole paragraph or line was affected by the change.

You can also compare two different revisions by clicking the *Compare any two revisions* checkbox at the top of the page.

If you'd like to restore a previous revision, click the *Restore This Revision* button.

The screenshot shows the WordPress 'Compare Revisions' interface for a post titled "Hello world!". The interface includes a sidebar with navigation options like Dashboard, Posts, Media, and Settings. The main content area shows a comparison between two revisions. A "Revisions Slider" is positioned at the top, with "Previous" and "Next" buttons. A "Restore This Revision" button is visible on the right. The content is divided into "Title" and "Content" sections. The "Content" section shows two columns of text: the left column has red highlights indicating removed content, and the right column has green highlights indicating added content. Callout boxes explain these highlights: "Removed Content" states "The red text shows content that was removed." and "Added Content" states "The green text shows content that was added."


Adding Images and Other Media

Adding images and other media files such as videos, documents or PDFs is extremely easy within WordPress. All your images and files are stored in the Media Library. Once they're uploaded into the Media Library, it's a very simple matter to insert them into your Page or Post content. In the case of files such as Word Documents or PDFs, if necessary, it's a simple process to create links to those files so that people can then download them.

Inserting an Image


Using the WordPress media manager, it's extremely simple to insert, align and link your individual images and image galleries.

To insert an image into your Page/Post, click the *Add Media* button

( Add Media) and then simply drag your image(s) from wherever they are on your computer, into the browser window. Your file(s) will be automatically uploaded.

Alternatively, click the *Select Files* button and then select the file(s) that you'd like to upload, using the dialog window that is displayed.

It's also possible to simply drag your image straight into the Visual Editor, rather than clicking the *Add Media* button.



No matter whether you've clicked the *Add Media* button or simply dragged and dropped your image into the Visual Editor, once your image is uploaded, your Media Library is displayed, which contains all your previously uploaded images. The image(s) that you've just uploaded will be automatically 'selected' for easy insertion into your Page or Post. Selected images are shown with a 'tick' icon in the top right corner of the image.

After uploading your image(s), you can then select other previously uploaded images by holding down the Ctrl key (Cmd key on Macs) and simply clicking on them. To deselect an image, click the 'tick' in the top right corner of the image.


At the bottom of the window you will see a count of the number of images currently selected.

There are several options within this *Insert Media* window to help make it easier to add images into your Page or Post.

By default, all previously uploaded images are shown, starting with the most recent uploads. If you'd like to narrow this list down, at the top of the window is a dropdown list that allows you to filter your displayed images by *All media items*, items *Uploaded to this post/page*, or just *Images*, *Audio* files or *Video* files. You can also filter your media files by selecting a date, or alternatively, there is also a *Search* field that allows you to search for specific images.

The properties of the currently highlighted image (i.e. The image with the blue border) will be shown on the right-hand side of the *Insert Media* window. These properties include the filename, the date the file was uploaded and the image size. It's at this point you can also change the image Title, Caption, [Alt Text](#) and Description for each image, as well as the Alignment, Link and the Size at which the image is inserted.

- **Title** – is displayed as a tooltip when the mouse cursor hovers over the image in the browser
- **Caption** – is displayed underneath the image as a short description. How this displays will be dependent on the WordPress theme in use at the time. You can also include basic HTML in your captions
- **Alt Text** – is displayed when the browser can't render the image. It's also used by screen readers for visually impaired users so it's important to fill out this field with a description of the image. To a small degree, it also plays a part in your website Search Engine Optimisation (SEO). Since search engines can't 'read' images they rely on the Alt Text
- **Description** – is usually displayed on the attachment page for the media, however this is entirely up to the theme that is currently in use



For each image, you can select how you would like the image aligned, either *Left*, *Center* or *Right* aligned, using the *Alignment* dropdown list. You can also select *None* for no alignment which will mean the image will display using the default alignment setting for your Theme.

You can also change what your inserted image(s) will link to using the *Link To* dropdown list. You have the choice of linking to the image's attachment page by selecting *Attachment Page*, or you can link to the full size image by selecting *Media File*. You can also link to any URL by selecting *Custom URL*. When you do this, a new field will appear that allows you to enter in the custom URL. You can also choose not to link to anything by selecting *None*.


When your image(s) are uploaded, WordPress will also create several copies of your file at various sizes. You can choose which one you'd like to insert into your Page or Post using the *Size* dropdown list. To insert the image at the exact size you

uploaded, simply select *Full Size*. Next to each size listed in this dropdown will be the actual dimensions of the image, in pixels (e.g. 300 x 225).

Once you've selected all your images, click the *Insert into post* button to insert the selected image(s) into your Post at the current cursor position (when editing a Page, this button will say *Insert into page*).


If you'd like to change the order of your images, click the *Edit Selection* link at the bottom of the *Insert Media* window. The window will change so that only the selected images are shown. Alternatively, clicking the *Clear* link will deselect all images.

After clicking the *Edit Selection* link at the bottom of the *Insert Media* window, all the currently selected images are shown. You can change the order in which the images will appear in your Page or Post by clicking and dragging each image to reorder them. You can also update the image Title, Caption, [Alt Text](#) and Description for each image. To remove one of your selected images, click the small 'x' that appears in the top right corner of the image.



Clicking the *Return to library* button will take you back to the previous screen that allows you to select or deselect your images.

When you're editing your Post/Page, if you wish to insert an image that you uploaded earlier (as opposed to uploading a new image), click the *Add Media*





button again ( **Add Media**). Once the pop-up window displays, click the *Media Library* tab at the top of the pop-up window rather than dragging a new file into the upload window. All your previously uploaded images will be displayed, with the most recent ones shown first.


Select the image(s) that you'd like to insert into your Page or Post and then simply click the *Insert into post* button (or if you're editing a Page, this button will say *Insert into page*). As mentioned earlier, you can also click the *Edit Selection* link at the bottom of the window if you'd like to change the order the images are inserted.


Edit or Delete an Image

There are various options available for adjusting the layout of inserted images.

After clicking on an image that has already been inserted into your Page or Post, a small toolbar will appear over the image. By selecting one of the alignment


buttons (   ) you can change the alignment of the inserted image.


Clicking the edit icon () allows you to edit the image properties. Clicking the


delete icon () will delete the image from your content. It will only remove the image from your Page or Post, it will not delete the image from your Media Library.

When you click on an image in your Page or Post, as well as the alignment, edit and delete icons mentioned above, the image also displays ‘resizing handles’. These are the small squares you see around the edge of the image. To resize your image, simply click and drag one of the corner resize handles.

As with any image editing software though, if you try to enlarge a small image, it will tend to get quite pixelated. It’s always best to insert a large image and then resize down.



After clicking the *Edit Image* icon () the following pop-up window will appear.



The Image Details pop-up window allows you to edit the various image and link properties:

- **Caption** – Displayed underneath the image as a short description. How this displays will be dependent on the WordPress theme in use at the time. You can also include basic HTML in your captions
- **Alternative Text** – Displayed when the browser can't render the image. It's also used by screen readers for visually impaired users so it's important to fill out this field with a description of the image. To a small degree, it also plays a part in your website Search Engine Optimisation (SEO). Since search engines can't 'read' images they rely on the Alt Text
- **Align** – Allows you to select how you would like the image aligned. They can be either Left, Centered or Right aligned. Setting alignment to None will

remove the other alignment settings. How this affects your image within your content will depend on the current theme in use

- **Size** – Select a specific size from the dropdown list or select ‘Custom Size’ and then enter the Width and Height (in pixels) in the input fields that appear
- **Link To** – Select where you would like to link your image to from the dropdown list. You have the choice of linking to the image attachment page by selecting *Attachment Page*, or you can link to the full size image by selecting *Media File*. You can also link to any URL by selecting *Custom URL*. When you do this, a new field will appear that allows you to enter in the custom URL. You can also choose not to link to anything by selecting *None*
- **Image Title Attribute** – Displayed as a tooltip when the mouse cursor hovers over the image in the browser
- **Image CSS Class** – By default, WordPress will assign several CSS Classes to your image. If, for some reason, there’s other CSS Classes that you’d like to assign to your image then you can add them into this input field
- **Link Rel** – Describes the relationship from the current document to the specified link. More information on the rel HTML attribute can be found on [Wikipedia](#)
- **Link CSS Class** – If there is a specific CSS Class that needs to be set on the HTML link then you can add it into this input field

Clicking the *Edit Original* button allows you to perform some simple manipulation with your uploaded image. You’re able to rotate and flip your image as well as scale and crop it to different sizes.


If you’d like to replace the image entirely, click the *Replace* button and you’ll be shown your Media Library where you can select a new image.

Once you have updated the image properties, click the *Update* button to save your changes. Alternatively, click the small ‘x’ in the top-right of the pop-up window to close the pop-up without saving any changes.

Setting a Featured Image


Some themes allow you to specify a Featured Image for your Page and Post. A Featured Image, often called a Post/Page Thumbnail, is usually some sort of image that is representative for that particular Page or Post. How these images are displayed is dependent entirely on the Theme that is currently in use.

If your Theme allows you to set a Featured Image, the following *Featured Image* panel will be displayed when you're editing your Page or Post. If Featured Images can't be set then this panel won't be displayed.



Setting your featured image is very similar to adding an image into your Page or Post. After clicking the *Set featured image* link a pop-up window will display that looks similar to the one that displays when you add an image to your Page/Post. You can upload a new image to use as your Featured Image or you can simply choose from one of your previously uploaded images.


By default, you'll be shown a list of the previously uploaded images. If you'd like to upload a new image, click on the *Upload Files* link at the top of the pop-up window. After clicking the image you'd like to use as your *featured image* you can then update the Title, Caption, Alt Text and Description. To set the image as your Featured Image, click the *Set featured image* button. Your chosen image will then appear in the *Featured Image* panel.



Insert an Image Gallery

WordPress has its own simple built-in Image Gallery that allows you to add multiple images to a page in one easy step.


To insert an image gallery into your Page/Post, click the *Add Media* button

( **Add Media**). A pop-up window will display that looks the same as the one that displays when you add an image to your Page/Post. You can upload new images to use in your gallery or you can simply choose from your previously uploaded images.

By default, you'll be shown a list of your previously uploaded images. If you'd like to upload a new image, click on the *Upload Files* link at the top of the pop-up window.

Click the *Create Gallery* link in the left-hand navigation then select the images that you'd like to insert into your gallery.

After selecting your images, click the *Create a new gallery* button at the bottom of the pop-up window. The window will change so that only the selected images are shown.



All the images that appear will be used within your Image Gallery. To reorder the images simply click on an image and drag it to its new position. If you'd like to add captions to your images, click the '*Caption this image..*' text below each image and then type in your caption. Alternatively, click each image and then update the Title, Caption, Alt Text and Description on the right-hand side of the pop-up window. You can also include basic HTML, such as links, in your captions.



If you decide you no longer want a certain image to appear in your gallery, click the small 'x' that appears in the top-right corner of the image.


Since the built-in gallery is quite simple, there aren't that many options to choose from when setting it up.

- **Link to** – This sets what happens when the thumbnail image is clicked. Selecting *Media File* will open the full size image directly in your browser window. Selecting *Attachment Page* will open the image within one of your WordPress formatted pages
- **Columns** – Specifies the number of columns to use when displaying your thumbnail images. Ultimately, this will be dependent on your Theme and how wide your page is. If you find the gallery isn't displaying properly after changing this number you may need to change it to another number
- **Random Order** – Click this checkbox to display your images in a random order
- **Size** – Selects the size of the image to use in your gallery

Edit or Delete an Image Gallery

Editing or Deleting an Image Gallery is much like editing or deleting an image. After clicking on an Image Gallery that has been inserted into your Page or Post,


two icons will appear on top of the gallery. Clicking the left icon () allows you to edit the image gallery properties. Clicking the right icon () will delete the image gallery from your content. It will only remove the image gallery from your Page or Post, it will not delete any images from your Media Library.



After clicking the Edit Gallery icon you will be shown the same pop-up window and options as when your image gallery was inserted into your Page/Post.

Insert an Audio or Video Playlist


Inserting an audio or video playlist is almost identical to inserting an image

gallery. Click the *Add Media* button (). A pop-up window will display that looks the same as the one that displays when you add an image to your Page/Post. You can upload new media files to use in your playlist or you can simply choose from your previously uploaded files.


By default, you'll be shown a list of your previously uploaded files. If you'd like to upload a new media file, click on the Upload Files link at the top of the pop-up window.

To create an audio playlist, click the *Create Audio Playlist* link in the left-hand navigation. The pop-up window will display a list of your audio files.

Alternatively, to create a video playlist, click the *Create Video Playlist* link in the left-hand navigation. The pop-up window will display a list of your video files.



After selecting your media files, click the *Create a new playlist* button at the bottom of the pop-up window. The window will change so that only the selected media files are shown.



All the media files that appear will be used within your playlist. To reorder the files simply click on a file and drag it to its new position. You can change the title for each file by clicking the text below each file and then typing in your new title. Alternatively, click each file and then update the *Title*, *Caption* and *Description* on the right-hand side of the pop-up window.

If you decide you no longer want a certain media file to appear in your playlist, click the small 'x' that appears in the top right corner of the file when you hover your cursor over it.

You can change how your playlist appears in your page by selecting which items you'd like to appear.

When inserting an audio playlist you have the following display settings.


- **Show Tracklist** – Ticking this checkbox will show a list of all the audio files within your playlist

- **Show Artist Name in Tracklist** – Ticking this checkbox will show the artists name next to each track name
- **Show Images** – Ticking this checkbox will show any associated audio file images

When inserting a video playlist you have the following display settings.

- **Show Video List** – Ticking this checkbox will show a list of all the video files within your playlist
- **Show Images** – Ticking this checkbox will show any associated video file images

Inserting Video, Audio or Other File Type

The procedure for inserting any other type of file into your Page/Post is exactly the same as Inserting an Image. Simply click the *Add Media* button (). Once the relevant pop-up window displays, perform the same steps to upload your file to your site and to insert it into your Page or Post.

When inserting video or audio files, you can select *Embed Media Player* from the *Embed or Link* dropdown list in the Insert Media pop-up window to use the new audio and video players that are now built into WordPress. Supported audio/video formats include M4a, MP4, OGG, WebM, FLV, WMV, MP3, WAV and WMA files.



It's recommended that you make your filename 'server friendly'. Make sure the filename has no spaces, apostrophes, slashes or other non-alphanumeric characters (such as \$, % and &). Rename the file before uploading if it does. To preserve readability, some people replace spaces with the underline character or hyphen. For instance, *My File Name.txt* becomes *My_File_Name.txt* or *My-File-Name.txt*


Embedding a Video, Image or Other Content

Another way to add video or other content into your pages is through embedding. A popular example of this is embedding a YouTube video into your page.


When you're embedding a file, there's no need to upload the file to your site. You're basically just creating a link to the file, from within your own page.

WordPress is able to automatically embed files from a number of different services.

To embed something into your Post or Page, simply paste the URL into your content area. The URL needs to be on its own line and not hyperlinked.



When embedding content in this manner (as opposed to using the embed shortcode mentioned below), your url will change to show a preview of that content. For example, when embedding a video from YouTube, after pasting in the URL to the editor, it will magically change to show the actual video content, right there in the editor.



If you'd like to specify the width and height, you can wrap the URL in the *[embed] shortcode*. Embedding your link using this shortcode does not require the URL to be on its own line. The format for using the shortcode is:

```
[embed width= "123" height= "456"] url [/embed]
```

WordPress will automatically embed content from the following sites:


- [Animoto](#)
- [blip.tv](#)
- [CollegeHumor](#)
- [DailyMotion](#)
- [EmbedArticles](#)
- [Flickr](#)
- [FunnyOrDie.com](#)
- [Hulu](#)
- [Imgur](#)
- [Instagram](#)
- [iSnare](#)
- [Issuu](#)
- [Meetup.com](#)
- [Mixcloud](#)
- [Photobucket](#)
- [Polldaddy](#)
- [Rdio](#)
- [Revision3](#)
- [Scribd](#)
- [SlideShare](#)
- [SmugMug](#)


- [SoundCloud](#)
- [Spotify](#)
- [TED](#)
- [Twitter](#)
- [Vimeo](#)
- [Vine](#)
- [WordPress.tv](#)
- [YouTube](#) (only public and "unlisted" videos and playlists)

Adding HTML Links

HTML links allow your site visitors to easily navigate around your site. They're also used when you want to allow people to download files from your site, such as PDFs or other documents, for viewing images or even just linking to other websites. HTML links will frequently be shown with an underline to differentiate it from other text, but this may vary depending on the theme you're currently using.

Inserting an HTML Link

Inserting an html link in your Page/Post to one of your own pages or another site is extremely easy. Simply click and drag the cursor and highlight the text that you want turned into a link and then click the *Insert/edit link* button (). As well as being able to insert a link to another site, you can also easily insert a link to one of your existing Posts or Pages by simply selecting it from a list.




In the pop-up window that is displayed, simply fill in URL and the Title and then click the *Add Link* button.

- **URL** – URL of the page or website that you would like to create a link to
- **Title** – The text to display in *tooltip* form when the cursor hovers over the link
- **Open link in a new window/tab** – When someone clicks the link you can have it open in the same window (default setting) or have it open in a new browser window/tab

Alternatively, if you'd like to add a link to one of your existing Posts or Pages, simply click the *Or link to existing content* link to display a list of your existing content then select the relevant page from the supplied list. If you have a large number of pages within your site, you can type the Page or Post name in the *Search* field to make it easier to find. As you type, the list will re-populate based on matching results. After selecting one of your existing pages, the relevant details will be updated in the *URL* and *Title* fields. Click the *Add Link* button to add your link.


Inserting Links to Media Files

Adding a link to media files such as documents or PDF's is just as easy as adding a standard html link. There are a couple of ways you can go about it.

Click the *Add Media* button () and then simply drag your file from wherever it is on your computer, into the browser window. Your file will be automatically uploaded.


Alternatively, click the *Select Files* button and then select the file that you'd like to upload, using the dialog window that is displayed.

Once your file is uploaded, your Media Library, which contains all your previously uploaded files, is displayed. The file that you've just uploaded will be automatically 'selected' for easy insertion into your Page or Post.




Update the *Title* for your file. The *Title* will be used for the text link when it's inserted into your content. From the *Link To* dropdown list, select *Media File*. The field just below this will be automatically populated with the URL for the file.


Click the *Insert into post* button to insert a link to the selected file in your Post at the current cursor position (when editing a Page, this button will say *Insert into page*).

If you happen to know the URL for the media file that you'd like to link to or if you'd like to create a link on some existing text, simply click and drag the cursor and highlight the text that you want turned into a link and then click the *Insert/edit link* button (). Just like previously, when adding a simple HTML link, enter the URL to your media file and the Title and then click the *Add Link* button. A standard html link will be created that links to the media file that you specified.

Editing an HTML Link

Simply click the link within your Page/Post that you'd like to edit, to position the cursor somewhere within it and then click the *Insert/edit link* button (). A pop-up window will appear, just like when the link was originally inserted. Update the required details and click the *Update* button.

Removing an HTML Link

To remove an html link, click the link within your post that you'd like to remove, to position the cursor somewhere within it and then click the *Unlink* button (). If you want to remove a link from an image, simply click the image once to select it and then click the *Unlink* button. If the html link is linking to an uploaded file or image, clicking the *Unlink* button won't remove or delete that file, it will simply remove the hyperlink.

Editing Existing Content


To edit an existing page, simply click on the relevant Page/Post title, when viewing your list of Pages or Posts. Alternatively, click on the *Edit* link that appears beneath the title when hovering your cursor over each row.




The screen that appears will be exactly the same as the *Add New Page/Add New Post* screen, only with the existing content displayed. When you've finished editing your Page/Post, click the *Update* button.

Deleting Content

If you wish to delete one of your Pages or Posts, click on the *Trash* link that appears beneath the title when hovering your cursor over each row. This will move the Page/Post to the Trash.





To delete the Page/Post permanently or to restore the Page/Post, click the *Trash* link at the top of the screen. When the cursor is hovering over each item in the Trash, the *Restore* and *Delete Permanently* links appear. Click *Delete Permanently* to permanently remove a single Page or Post. Clicking *Restore* will restore the Page or Post.



If you would like to permanently delete or restore numerous items at once, click the checkboxes next to the items you would like to delete or restore and then choose either *Restore* or *Delete Permanently* from the *Bulk Actions* dropdown list at the top of the page. After selecting the appropriate action click the *Apply* button to make your change. Alternatively, click the *Empty Trash* button to delete all the items in the Trash.

Fullscreen Editing

WordPress allows for fullscreen composing. It provides for complete distraction free editing of your Page or Post. To enter fullscreen mode simply click on the *Distraction Free Writing* button (). With the Distraction Free Writing button turned on, the left-hand menu and the right-hand side panels fade out of view, leaving the screen with just the minimal required to compose your content.




In Distraction Free Writing mode, only the Title field and Visual Editor is displayed until you move your cursor outside of the editor. Once you move your cursor outside of the editor, the menu and side panels fade back into view.

To exit from Distraction Free Writing mode, click on the *Distraction Free Writing* button again.

Saving and Publishing Content

Once you've added all your content to your Page or Post you have the option of Saving the Page as a Draft or Publishing the page. Clicking the *Save Draft* button will simply save your Page/Post. This is handy if you would like to come back at a later date to add more content or if you're simply not ready to publish yet.



Clicking the *Publish* button will save your Page/Post and publish it on your website.

Clicking the *Preview* button will show you a preview of the current Page/Post.

There are also several options available when saving. By default the *Status* is set to Draft but this can be changed by clicking the *Edit* link just to the right of *Status*: within the *Publish* panel.

- **Pending Review** means the draft is waiting for review by an editor prior to publication.
- **Draft** means the post has not been published and remains a draft for you.

You can also change the visibility of the Page by clicking the *Edit* link just to the right of *Visibility*: within the *Publish* panel.

- **Public** is the default and means the page is viewable to all. There is also an option to make the Post ‘sticky’. Sticky posts are placed at the top of all blog posts and stay there even after new posts are published.
- **Password Protected** allows you to assign a password to your page. Only people who have the password will be able to access the page.
- **Private** hides the content from the public completely. Normal users and visitors will not be aware of private content. You will only see the private content when you are logged into your WordPress blog.

By default, when you click the *Publish* button your Page/Post is published immediately. To change this, click the *Edit* link just to the right of *Publish immediately* within the *Publish* panel. You can then select the date and time that you’d like to schedule your Page/Post to be published. You must also click the *Publish* button when you have updated the date and time fields to publish at the desired date and time.

Categories

You can use categories to define sections of your site and group related posts. The default category is *Uncategorized* but this can be easily changed in your Settings. Pages cannot be associated with Categories. You can only associate Categories to Posts.

There are two ways to add Categories. They can be added whilst adding or editing your Post or they can be added via the *Categories* menu option. Adding Categories whilst editing your Post, will automatically assign those Categories to your Post. Adding Categories using the *Categories* menu option will simply add them to the list of available Categories.

When you click on the *Categories* menu option you'll be shown a list of Categories that have already been added along with some blank fields that allow you to add a new Category.

Add New Category

Add a new Category by filling in the Name, Slug, Parent (if any) & Description.

Add New Category

After filling in all the fields, click the Add New Category button to add a new Category.

Name	Description	Slug	Posts
aciform		aciform	1
— sub		sub	1
antiquarianism		antiquarianism	1
arrangement		arrangement	1
asmodeus		asmodeus	1
Blogroll		blogroll	0
dispatch		dispatch	1
echappee		echappee	1
Edge Case	Posts that have edge-case related tests	edge-case-2	6
enphagy		enphagy	1

Note:
 Deleting a category does not delete the posts in that category. Instead, posts that were only assigned to the deleted category are set to the category Uncategorized.
 Categories can be selectively converted to tags using the [category to tag converter](#).

To add a new Category, fill in the blank fields and then click the *Add New Category* button:

- **Name** – The name is how it appears on your site

- **Slug** – The Slug is the URL-friendly version of the name. It's usually all lowercase and contains only letters, numbers, and hyphens
- **Parent** – Categories, unlike tags, can have a hierarchy. You might have a Car category, and under that have children categories for Ford, General Motors and Toyota. Totally optional. To create a subcategory, just choose another category from the *Parent* dropdown
- **Description** – The description is not prominent by default; however, some themes may display it

Once you add a new Category it will appear in the list of Categories on the right side of the screen.

When hovering your cursor over each row in the list of Categories, a few links will appear beneath the Category name.

- **Edit** – Allows you to edit the Category properties such as Name, Slug, Parent and Description
- **Quick Edit** – Allows you to quickly edit the Category Name and Slug
- **Delete** – Deletes the Category permanently from the list of Categories. After clicking Delete you will be prompted to confirm your choice. Click *OK* to delete the Category or *Cancel* if you don't want to delete it
- **View** – This will list all the Posts that are currently using this Category

If you would like to permanently delete numerous Categories at once, click the checkboxes next to the Categories you would like to delete and then choose *Delete* from the *Bulk Actions* dropdown list at the top of the page. After selecting Delete, click the *Apply* button to immediately delete the selected Categories (you will not be prompted to confirm your choice).

Deleting a Category does not delete the posts in that Category. Instead, posts that were only assigned to the deleted Category are set to the default Category, which is set to *Uncategorized* by default. The Default Post Category can be configured within the *Settings > Writing* section.

Adding Categories within your Post

Adding Categories whilst editing your Post will automatically assign those Categories to your Post.

When adding or editing your Post, the *Categories* panel can be found just below the *Format* panel if your Theme supports Post Formats. Alternatively, it will reside just below the *Publish* panel. To add an existing Category, simply tick the checkbox(es) next to the Categories you'd like to assign to the Post.

The screenshot shows the WordPress post editor interface. On the left is a dark sidebar with navigation options: Plugins, Users, Tools, Settings, and Collapse menu. The main content area displays a post URL, a paragraph of text, and a 'Path: p' field. On the right, the 'Format' panel is open, showing the 'Categories' section. This section has two tabs: 'All Categories' and 'Most Used'. Under 'All Categories', there is a list of categories with checkboxes: 'Uncategorized', 'aciform', 'sub', 'antiquarianism' (checked), 'arrangement', 'asmodeus', 'Blogroll' (checked), and 'broder'. Below this list is a '+ Add New Category' link, an empty input field, a 'Parent Category' dropdown menu, and an 'Add New Category' button. Two callout boxes are overlaid on the image. The first, titled 'Add Existing Category', points to the checked categories and contains the text: 'To add an existing Category, tick the checkbox(es) next to the appropriate Categories to assign them to the Post.' The second, titled 'Add New Category', points to the '+ Add New Category' link and contains the text: 'To add a new Category, click the + Add New Category link and type in the Category name. Select the Parent Category from the list if appropriate. Click the Add New Category button to assign it to the Post.'

If you would like to create a new Category and assign it to the Post at the same time, click the + *Add New Category* link. Two fields will then appear. Type the name of the Category that you'd like to add into the empty input field. If you'd like the new Category to have a Parent, select it from the *Parent Category* dropdown list. Click the *Add New Category* button when done to create the Category and automatically assign it to the Post.

Tags

Tags are ad-hoc keywords that identify important information in your post (names, subjects, etc) that may or may not recur in other posts. Unlike Categories, Tags have no hierarchy, meaning there's no relationship from one Tag to another. Pages cannot be assigned Tags and cannot be associated with Categories. You can only associate Tags and Categories to Posts.

Like Categories, there are two ways to add Post Tags. They can be added whilst adding or editing your Post or they can be added via the *Tags* menu option. Adding Tags whilst editing your Post, will automatically assign those Tags to your Post. Adding Tags using the *Tags* menu option will simply add them to the list of available Tags.

When you click on the *Tags* menu option you'll be shown a list of Tags that have already been added, along with some blank fields that allow you to add a new Tag. A list of popular Tags is also displayed in 'cloud' format. That is, the Tags are displayed in alphabetical order and the more often a Tag has been used, the larger the font it's displayed in.

The screenshot displays the WordPress 'Tags' management interface. On the left is a sidebar with navigation links. The main area shows a list of tags with columns for Name, Description, Slug, and Posts. A 'Add New Tag' button is present, and a tooltip explains that hovering over each row shows various options you can perform. Another tooltip explains that after filling in all the fields, clicking the 'Add New Tag' button will add a new tag.

To add a new Tag, fill in the blank fields and then click the *Add New Tag* button:

- **Name** – The name is how it appears on your site

- **Slug** – The Slug is the URL-friendly version of the name. It's usually all lowercase and contains only letters, numbers, and hyphens
- **Description** – The description is not prominent by default; however, some themes may display it

Once you add a new Tag it will appear in the list of Tags on the right side of the screen.

When hovering your cursor over each row in the list of Tags, a few links will appear beneath the Tag name.

- **Edit** – Allows you to edit the Tag properties such as Name, Slug and Description
- **Quick Edit** – Allows you to quickly edit the Tag Name and Slug
- **Delete** – Deletes the Tag permanently from the list of Tags. After clicking Delete you will be prompted to confirm your choice. Click *OK* to delete the Tag or *Cancel* if you don't want to delete it
- **View** – This will list all the Posts that are currently using this Tag

If you would like to permanently delete numerous Tags at once, click the checkboxes next to the Tags you would like to delete and then choose *Delete* from the *Bulk Actions* dropdown list at the top of the page. After selecting Delete, click the *Apply* button to immediately delete the selected Tags (you will not be prompted to confirm your choice).

Adding Tags within your Post

Adding Tags whilst editing your Post, will automatically assign those Tags to your Post.

When adding or editing your Post, the *Tags* panel can be found just below the *Categories* panel. To add an existing Tag, click the *Choose from the most used tags* link. This will display a list of previously used Tags (if available). They are arranged alphabetically and in 'cloud' format. That is, the more often a Tag has been used, the larger the font it's displayed in. To add a previously used Tag, simply click on the Tag name and it will be assigned to your Post. To add a new Tag, simply write the Tag or Tags (separated with commas) into the edit field and

click the *Add* button. Tags that are assigned to the Post will be displayed below the edit field. To remove a Tag from your Post, click the small 'x' icon next to the Tag name.

The screenshot shows the WordPress post editor interface. On the left is a dark sidebar with navigation options: Categories, Tags, Media, Pages, Comments, Appearance, Plugins, Users, Tools, Settings, and Collapse menu. The main content area shows a post titled "Enterprise. Its five-year mission: to explore strange new worlds, to seek out new life and new civilizations, to boldly go where no man has gone before. We believe in what we're doing. Now it's time to go." Below the title is a text block: "Spaceflights cannot be stopped or even a group of men. It is a high priority for NASA, carrying out in accordance with the development." The post metadata shows "Path: p", "Word count: 145", and "Last edited by Joe Blogg on December 23, 2013 at 6:43 pm".

The **Tags** section is highlighted with a white box. It contains an input field, an **Add** button, and a list of existing tags: tag1, tag2, tag3. Below the tags is a link: [Choose from the most used tags](#). A list of popular tags is shown, including: [8BIT](#), [alignment](#), [Articles](#), [aside](#), [audio](#), [captions](#), [categories](#), [chat](#), [Codex](#), [comments](#), [content](#), [css](#), [dowork](#), [edge](#), [case](#), [embeds](#), [excerpt](#), [Fail](#), [featured](#), [featured](#), [image](#), [formatting](#), [FTW](#), [Fun](#), [gallery](#), [html](#), [image](#), [jetpack](#), [layout](#), [link](#), [lists](#), [Love](#), [markup](#), [media](#), [Mothership](#), [Must Read](#), [Nailed It](#), [Post Formats](#), [quote](#), [shortcode](#), [standard](#), [template](#), [title](#), [twitter](#), [video](#), [videopress](#), [wordpress.tv](#).

Two callout boxes provide instructions:


- Add New Tag:** To add a new Tag, write the Tag or Tags (separated with commas) into the edit field & then click the *Add* button to assign it to the Post.
- Add Existing Tag:** To add an existing Tag, click the *Choose from the most used tags* link and click the appropriate Tag or Tags from the list to automatically assign it to the Post.

At the bottom of the Tags section, there is a featured image of a space station in orbit and a link: [Remove featured image](#).


Media Library

The Media Library is where you can find all the files that you've uploaded. In WordPress 4.0 and above there are two different types of views you can select from when viewing your media library. You can click the List View icon (☰) to display your images in a list, similar to how they've been displayed in previous versions of WordPress, or you can click the Grid View icon (田) to view your images in the new Grid layout.

The Grid View will display a grid of thumbnail images for each of your media files. The Grid View employs infinite scrolling, rather than displaying your images over multiple pages. To view more images, simply scroll to the bottom of the page and more thumbnails are automatically loaded.



The List View will display your images similar to how they've been displayed in previous versions of WordPress, in a list over multiple pages.



Both views show the most recently uploaded files first. There are also dropdown lists that allow you to filter the list of files that are currently being displayed, along with a search field to help search for files.

Within the List View, the list of files contains a small thumbnail version of the image or file, the file name and the type of file (JPG, MP3, etc.), the name of the Author who uploaded the file, the Page or Post which the image was uploaded to, the number of comments and the date the file was uploaded.

When hovering your cursor over each row in the List View, a few links will appear beneath the file name.

- **Edit** – Allows you to edit the file properties such as Title, Alt Text, Caption and Description. You can also perform some basic image manipulation

- **Delete Permanently** – Deletes the file permanently from the Media Library
- **View** – Will take you to the display page for that file

Viewing a File in the Media Library

The Grid View will display a grid of thumbnail images for each of your media files. Depending on the file type, you'll either see a thumbnail image for that particular file or an icon representation.


After clicking on a thumbnail within the Grid View, a pop-up window will display the properties for that particular file. If the file is an image, you'll also see a larger version of that image. For supported audio and video files (M4a, MP4, OGG, WebM, FLV, WMV, MP3, WAV and WMA) you'll see the appropriate media player. For other file types such as PDF's or Word Documents, there is a link to view the attachment page which has a link to the actual file.

The screenshot shows the 'Attachment Details' pop-up window in WordPress. On the left is a large image of a spaceship (Serenity) in space. Below the image is an 'Edit Image' button. On the right is a form with the following fields:

- File name: Serenity.jpg
- File type: image/jpeg
- Uploaded on: December 22, 2013
- File size: 152 kB
- Dimensions: 1024 x 768
- URL:
- Title:
- Caption:
- Alt Text:
- Description:
- Uploaded By: Joe Blogg
- Uploaded To: [Hello world!](#)

At the bottom of the form are three links: [View attachment page](#), [Edit more details](#), and [Delete Permanently](#). Two callout boxes provide instructions: one says 'Update the media file properties by filling in the relevant fields. The available fields will vary depending on the type of file you're updating.' and the other says 'To view and edit more file properties, click the *Edit more details* link.'

Within the List View, hover the cursor over one of the rows and click the *View* link. If the file is an image, you'll see a larger version of that image. For supported audio and video files (M4a, MP4, OGG, WebM, FLV, WMV, MP3, WAV and WMA) you'll see the appropriate media player. For other file types such as PDF's or Word Documents, you'll see the attachment page which has a link to the actual file.




Adding a File to the Media Library

To add a new file to the Media Library, click on the *Add New* link in the left-hand navigation menu or the *Add New* button at the top of the page.


If you click the *Add New* button when you're viewing the Media Library in the *List View*, or click the *Add New* link in the menu, simply drag your images from wherever they are on your computer, into the area marked *Drop files here*. Your file(s) will be automatically uploaded.

Once your images or files are uploaded, they're listed below the file uploader. If you'd like to edit the file properties, click the *Edit* link next to the file.



If you click the *Add New* button when you're viewing the Media Library in the *Grid View*, you can drag your images from wherever they are on your computer, to anywhere on the screen. Your file(s) will be automatically uploaded.

Once your images or files are uploaded, they're displayed below the file uploader, with the rest of your media.




When uploading files, you can also click the *Select Files* button and then select the files that you'd like to upload, using the dialog window that is displayed.

Editing the File Properties


If you're viewing your files using the *Grid View*, simply click on one of your media files and you'll be presented with a pop-up window that displays the relevant properties for that particular file.

After updating each field your changes will be automatically saved. You can use the arrow buttons at the top of the pop-up window to navigate to the previous or next image. Click the 'x' in the top-right of the pop-up window to return to the media Grid View.



To edit the properties of an existing file when using the *List View* within the Media Library, hover the cursor over the particular row that contains the file you wish to edit and click the *Edit* link. Alternatively, you can also click the file title or the thumbnail image. Clicking the *Edit* link next to the file after it's just been uploaded, will also allow you to edit its properties.

After clicking *Edit*, the relevant properties for that particular media file are displayed, including the title, URL, filename, file type and in the case of an image, the file dimensions. When editing the file properties, the *Alternative Text* field will only be displayed for images.



- **Title** – Although the field isn't labelled, the *Title* is the field at the very top of the page (when editing the image from the *List View*). The Title is displayed as a tooltip when the mouse cursor hovers over the image in the browser
- **Caption** – is displayed underneath the image as a short description. How this displays will be dependent on the WordPress theme in use at the time. You can also include basic HTML in your captions

- **Alternative Text** – This field is only displayed for image files. The Alternative Text is displayed when the browser can't render the image. It's also used by screen readers for visually impaired users
- **Description** – This content is displayed on the file's attachment page
- **Metadata - Artist** – This field is only displayed for audio files. It allows you to specify the recording artist
- **Metadata - Album** – This field is only displayed for audio files. It allows you to specify the album to which the audio file belongs to


Once the file properties are updated click the *Update* button to save your changes.

Editing an Image


WordPress has a basic image editing tool that allows you to perform some simple manipulation with your uploaded images. You're able to rotate and flip your images as well as scale them and crop them to different sizes.

When editing the file properties of an image (as opposed to other file types like documents or PDFs), click the *Edit Image* button that appears just below the image to show the image editing tools.

If you click the *Edit Image* button whilst using the *Grid View*, the image editing tools will appear in the pop-up window.



If you click the *Edit Image* button whilst using the *List View*, your page will look slightly different to the above *Grid View*. As well as the image editing tools, you'll also see the properties of the file such as the file size and dimensions. You can also still update the *Caption*, *Alternative Text* and *Description*.



No matter what view you're using, just above the image you'll find the following image editing buttons:



Crop – Click on the image and drag the selection box to the size that you'd like the image cropped. Click the Crop button to crop the image to the new size



Rotate counter-clockwise – Rotate the image 90° counter-clockwise



Rotate clockwise – Rotate the image 90° clockwise



Flip vertically – Flip the image vertically



Flip horizontally – Flip the image horizontally



Undo – Undo the last change



Redo – Redo the last change

To scale your image to a new size, simply enter the *width* or *height* dimensions in the appropriate field and click the *Scale* button. For best results, scaling should be done before performing any other operations like cropping, flipping or rotating the image. It's important to note that images can only be scaled down, not up.

After entering one scale value, the other value will change automatically so as to keep the image in proportion. The original image dimensions are displayed just above the input fields, for your reference.

There are several ways to crop your image. The easiest is to simply click on the image and drag the selection box to the appropriate size. If you'd like your image cropped to a specific ratio, enter the values in the *Aspect Ratio* input fields (e.g. 1:1 (square), 4:3, 16:9 etc.). You can then hold down the *shift* key and drag one of the edges of your selection to enlarge or reduce the size, while keeping this aspect ratio locked. If there is already a selection made, specifying the aspect ratio will automatically change the selection to match it.


Whenever the selection box is adjusted, the dimensions are displayed in the *Selection* input fields. You can also manually enter the dimensions of the selection box (in pixels) by entering values into these two fields. Once your selection box is adjusted, simply click the *Crop* button just above the image to crop the image to this new size.

By selecting one of the options in the *Thumbnail Settings* panel, you have the option to apply your changes to *All image sizes*, just the *Thumbnail* image or *All sizes except Thumbnail*.

Click the *Save* button to save your changes.

Click the *Update* button to return to the main Media Library page.

If you'd like to revert back to your original image, click the *Edit Image* button again to return to the image editor. A new *Restore Original Image* link is displayed just below the *Scale Image* link. Click the *Restore Original Image* link and then click the *Restore image* button to discard your changes and restore your original image.



Deleting a File from the Media Library

To delete a file from the Media Library when using the *Grid View*, first click an image to view the File Properties, then click on the *Delete Permanently* link that appears in the pop-up window.

To delete a file from the Media Library when using the *List View*, click on the *Delete Permanently* link that appears beneath the file name when hovering your cursor over each row.

After you click the *Delete Permanently* link in either view, you'll be prompted with a confirmation message.


Click the *OK* button to delete the file or click the *Cancel* button to return to the Media Library.

Comments

Comments are a feature of blogs which allow readers to respond to Posts. Typically, readers simply provide their own thoughts regarding the content of the post, but they may also provide links to other resources, generate discussion, or simply compliment the author for a well-written post. Comments allow you to interact more with your site visitors as well as generate feedback and discussion on your Posts.

Comments can be controlled and regulated through the use of filters for language and content, and if you prefer, can also be queued for approval before they are visible on the web site. This is useful in dealing with [comment spam](#).

When you click on the *Comments* menu option, you'll be shown a list of all the comments on your site.



At the top of the screen there are links that allow you filter the comment list to only show the comments that are Pending, Approved, Marked as Spam or that are

in the Trash. The number in brackets will advise how many there are for that particular type.

As well as the standard settings that allow you to manage your comments, the default WordPress install comes with an excellent plugin that helps to filter out spam from your comments. This plugin is called Akismet.

After activating the Akismet plugin, you need to supply it with an API Key. You can grab an API key and find out more information on the [Akismet website](#).

When hovering your cursor over each row in the list of Comments, a few links will appear beneath the comment.


- **Unapprove/Approve** – Allows you to unapprove the comment. This will stop it displaying on your site. If the comment is already unapproved then this link will change to *Approve*, to allow you to approve the comment
- **Reply** – Allows you to write a reply comment
- **Quick Edit** – Allows you to quickly edit the commenter's Name, Email or URL as well as the actual comment
- **Edit** – Allows you to edit the commenter's Name, Email or URL as well as the actual comment. It also allows you to mark the comment as either Approved, Pending or Spam and change the Date and Time
- **Spam** – Allows you to mark the comment as spam
- **Trash** – Allows you to mark the comment as Trash. Once it's in the Trash, you can either restore it if you made a mistake, or delete it permanently

If you would like to change the status of numerous Comments at once, click the checkboxes next to the Comment(s) you would like to change and then choose either *Unapprove*, *Approve*, *Mark as Spam* or *Move to Trash* from the *Bulk Actions* dropdown list at the top of the page. After selecting the appropriate option, click the *Apply* button.

Replying to a Comment

To respond to a comment that someone has written on one of your Posts, simply hover the mouse over the comment and click the *Reply* link when it appears. An

edit field will then appear beneath the comment where you can type your reply.



When you've written your comment, click the *Reply* button or alternatively, click *Cancel* to stop replying and cancel your editing.

The editor that appears when replying or editing a comment (using either the *Reply*, *Quick Edit* or *Edit* links) is much like the editor when creating or editing a Page or Post, only not as intuitive. At the top of the editor there are numerous formatting buttons. These buttons provide you with basic html formatting capabilities when composing a new reply comment or editing an existing comment.

The buttons work in two ways. Clicking a button without highlighting any text first, will simply insert the opening html tag relevant for that button. As an example, clicking the *Bold* button will insert the `` html tag into your comment. Clicking the *Bold* button again will close the tag by inserting the closing `` tag. If you highlight some text prior to clicking a button, both the opening and closing tags will be inserted around that highlighted text. For example, highlighting the text, 'bold text', prior to clicking the *Bold* button will insert '`bold text`'.




Bold – Bold text



Italic – Italicise text



Link – Used to insert a website link. When the button is clicked a pop-up window will appear where you type in the URL that you would like to link to



Blockquote – Used as a way of showing a quote. How this looks will be entirely dependent on the Theme that your site is currently using



Delete - Used as a way of showing deleted text. How this looks will be dependent on the Theme but is usually done by showing the text with a strikethrough



Insert - Used as a way of showing inserted text. How this looks will be dependent on the Theme but is usually done by showing the text with an underline



Image – Used to insert an image into the comment. When the button is clicked a pop-up window will appear where you type in the URL of the image that you would like inserted



Unordered List – Used to insert an unordered (or un-numbered) list




Ordered List – Used to insert an ordered (or numbered) list



List Item – Used to insert a list item into your ordered or un-ordered list



Code – Used for indicating a piece of code




Close Tags – Used to close open tags. If for example, you clicked both the *Bold* and *Italic* buttons to insert their opening tags, clicking the close tags button will insert both of the matching closing tags, in the correct order

Editing a Comment

There are two ways to edit a comment. Once you hover over an individual comment you can click the *Quick Edit* link or the *Edit* link. Both perform a similar function except that the *Edit* option also allows you to mark the comment as either Approved, Pending or Spam as well as change the Date and Time.

Quick edit


Clicking *Quick Edit* will replace the comment with an editor that allows you to update the comment, the comment authors name, email address and URL.



Once you have finished, click *Update Comment* to save your changes or click *Cancel* to cancel your changes and return to the list of comments.

Edit

Clicking *Edit* will display the editor on a new page. Like the *Quick Edit* option, you can update the comment, the comment authors name, email address and URL. The *Edit* option also gives you the ability to set the comment Status and change the comment Date and time. The comment status can be set to *Approved*, *Pending* or *Spam*. You also have the option to move the item to the Trash by clicking on the *Move to Trash* link.




You can change the date and time that the comment was submitted by clicking on the *Edit* link next to the date and time. After clicking *Edit*, several fields appear below the original date and time. Update the fields if required and click the *OK* button to save the new date and time.

Once you have finished updating the comment, click the *Update* button to save your changes. If you want to cancel your changes, click the browser *Back* button or click on the *Comments* menu option to return to the list of comments.

Unapproving and Approving Comments


If an inappropriate comment has been submitted, you may wish to Unapprove it. This will stop the comment from displaying on your site. Unapproved comments will be displayed with a different coloured background within your list of comments. They will also be highlighted with a red vertical bar down the left side of the row. Hovering your cursor over the comment will display an *Approve* link instead of an *Unapprove* link.



Marking Comments as Spam and Trash

If a spam comment has been posted to your site you can mark it as spam simply by hovering your cursor over the comment and clicking the *Spam* link. If you're using the Akismet plugin and you come across a spam comment that Akismet missed, marking it as spam will help Akismet learn and it will be less likely to miss similar spam in the future.


If you simply want to remove a comment, hover your cursor over it and click the *Trash* link.



To empty the Trash, click on the *Trash* link at the top of the page to display all the comments that have been marked as Trash. This link will be displayed along with a number within brackets which indicates how many comments are marked as Trash. To permanently remove all these comments, click the *Empty Trash* button. You will not be prompted for confirmation.

To remove all the spam comments, click on the *Spam* link at the top of the page to display all the comments that have been marked as spam. This link will be displayed along with a number in brackets which indicates how many spam comments there are. To permanently remove all these comments, click the *Empty Spam* button. You will not be prompted for confirmation.

You can also delete a single spam comment permanently by clicking on the *Delete Permanently* link that appears when hovering your cursor over each row. You will not be prompted for confirmation.



If you find there are comments that have been marked as spam that shouldn't be, click the checkboxes next to them and select *Not Spam* from the *Bulk Actions* drop down at the top of the page. Click the *Apply* button to confirm your choice. Alternatively, click the *Not Spam* link that appears when hovering your cursor over each row.

Appearance

The various Appearance menus allow you to change how your site looks and behaves. If your site has been setup for you by a third party then it's more than likely that you won't need to change any of the settings in here.

Depending on the theme that your site is running, you may find that you don't have all the menu options listed here, or you may have a couple of different ones. The reason for this is that a couple of the options under the *Appearance* section are theme based. For example, the default Twenty Fourteen theme allows you to customize options for how your theme displays. Not all themes will have these option pages, or if they do, they may be under another menu entirely.


Selecting your Theme

The overall appearance of a WordPress site is controlled by the Theme. Although there is a default theme that comes installed with WordPress, most people will either download a new theme, purchase one, or have one custom designed and built. There are hundreds of places where themes can be downloaded for free and/or for a small fee. One of the best places to start looking for themes is in the official WordPress [Themes Directory](#).

Clicking on the *Appearance* menu option will default you at the Themes screen. The theme that is currently active is shown at the top left of the screen. The other themes shown are ones that are installed, but not currently in use. To see a preview of your site in another theme (that isn't currently active), you can click the *Live Preview* button associated with each theme. While the preview screen is displayed, you're able to click your site links to view your various pages in the new theme layout as well as make various theme changes. To change your site to another Theme, hover your cursor over the theme you'd like to activate and click the *Activate* button that appears underneath the Theme. Alternatively, if the preview window is displaying, you can click the *Save & Activate* button in the top left corner of the window to activate the theme.

To view more details about a particular theme, hover your cursor over a theme thumbnail image and click on *Theme Details*. A pop-up window will appear that displays a larger image along with the theme description and other details.

Clicking on the *Add New* button at the top of the page allows you to upload a new theme to your site as well as search the WordPress Themes Directory for new themes and install them directly from within your Dashboard.




Previewing and Customizing your Theme

As well as the ability to preview a theme, you can also update various theme settings all while previewing the changes live. The options that you can change will be dependent on the individual theme.

For the currently active theme, clicking the *Customize* button allows you to update various settings whilst also previewing those changes. Until you click the *Save & Publish* button, only the theme preview window is updated, not the theme on your live site.

For all other installed themes that are not currently active, click the *Live Preview* button to preview the theme, update its settings and activate the theme. Until you click the *Save & Activate* button, only the theme preview window is updated, not the theme on your live site.




Adding a new Theme

You're able to add new themes to your site right within the WordPress Dashboard. At the top of the *Themes* screen there is an *Add New* button. Click this button to search and add new themes into your site.

After clicking the *Add New* button, you'll be shown the *Add Themes* screen. It should look similar to the screen below. The *Add Themes* screen allows you to search and install themes directly from the official [WordPress Themes Directory](#). By default, the screen will show a list of Featured themes.

You can use the links at the top of the page to filter the results to see *Featured* themes, *Popular* themes or the *Latest* themes. Click the *Feature Filter* link to filter the results based on the Tags you specify. There are Tags for Colors, Layout, Features and Subject.


Alternatively, click the *Search themes...* input field and enter text to search for a specific theme.



Hovering your cursor over each theme thumbnail will display extra buttons. To view the details of a theme along with a preview, click the large *Details & Preview* button or the smaller *Preview* button. Clicking the *Install* button will download and install the theme on your site. After the theme is installed, you will be given the choice to view a *Live Preview*, immediately *Activate* the theme or return to the *Theme Installer*.

Customizing your Site

Using the Customizer, you can modify certain parts of your website. When you click on the *Customize* menu option you'll be shown the various theme options that you can change. Depending on the theme that is currently in use, you may see more or less options than those displayed in the following image.



Clicking the small arrows will open and close each of the panels, giving you access to each of the various options. You'll find that some of the options in the Customize screen are also available via other menu options. As an example, you can change the *Site Title* and *Tagline* using the *General* option under the *Settings* menu.

As you make your changes on the left-hand side of the Customize screen, the theme preview on the right-hand side is automatically updated.

Until you click the *Save & Publish* button, only the theme preview is updated, not the theme on your live site.

Widgets

Widgets are independent sections of content that can be placed into any widgetized area provided by your theme. Although these widgetized areas are commonly called 'Sidebars' and are quite often located in the left or right-hand column, they can be also located anywhere within your site and are entirely

dependent on the current theme as to their location. Lots of themes use these widgetized sidebars in the footer area.

There are numerous widgets available by default which allow you to add extra content to your site, such as Recent Comments, Categories or Custom Menus, just to name a few. New Widgets can also be installed via plugins and again, depending what the plugin is used for the extra functionality it brings to your site will vary.

The screenshot shows the WordPress Widgets management interface. On the left is a sidebar menu with 'Appearance' selected. The main area is titled 'Widgets' and is divided into 'Available Widgets' and 'Inactive Widgets' sections. The 'Available Widgets' section contains several widget panels, some of which are expanded to show settings. The 'Inactive Widgets' section at the bottom shows widgets that have been removed from the sidebar but whose settings are preserved.

Available Widgets
 To activate a widget drag it to the sidebar. To deactivate a widget and deactivate it, drag it back.

Available Widgets
 The *Available Widgets* section contains all the widgets you can choose from.

Adding Widgets
 Once a widget is added to the sidebar, it will expand to show available options (if any). Click the *Save* button to save your changes.

Deleting Widgets
 Click the *Delete* link to delete the widget from the sidebar. Click the *Close* link to close the widget panel.

Adding Widgets
 To populate a sidebar, drag & drop a widget to the desired location.

Inactive Widgets
 If you want to remove a widget from a sidebar but keep its settings, drag it to the *Inactive Widgets* section.

Available Sidebars
 These are the available sidebars for the current theme. Click the title bar to expand them.

The *Available Widgets* section contains all the widgets you may choose from. To populate one of your Sidebars, drag and drop a widget to the desired location. Once the Widget is dragged to a Sidebar, the widget will open up to allow you to configure its settings. Click the *Save* button within the Widget to save your settings.

If you want to remove a widget from a Sidebar but save its settings for future use, drag it into the *Inactive Widgets* section. If you simply want to delete the Widget from your Sidebar, click the *Delete* link within the Widget.

The small arrow next to the Sidebar title will toggle the sidebar open and closed. If you drag and drop a widget onto a closed sidebar, the sidebar and widget will automatically open.

Updating the Menu

If your theme supports custom menus, you can make modifications to them from the *Menus* option. Menus can contain links to Pages, Posts, Categories, Custom Links or other content types.

The screenshot shows the WordPress 'Edit Menu' interface. The left sidebar contains navigation options: Dashboard, Posts, Media, Pages, Comments, Appearance (highlighted), Themes, Customize, Widgets, Menu, Header, Background, Editor, Plugins, Users, Tools, Settings, and Collapse menu. The main content area has two tabs: 'Edit Menu' (active) and 'Manage Locations'. Below the tabs, there's a dropdown menu for 'Short (Top primary menu)' and a 'Select' button. A 'Save Menu' button is visible in the top right.

Five instructional callouts are overlaid on the interface:

- Add Menu Item:** Add a menu item by ticking the appropriate checkbox & then clicking the *Add to Menu* button.
- Select Menu:** If your Theme supports multiple menus, choose one from the dropdown and click the *Select* button to edit it. Alternatively, click *create a new menu* to create a new menu.
- Moving Menu Items:** To move the menu options, you can use the provided links or simply drag 'n drop each one to a new position.
- Opening Menu Panels:** Open and close the various panels by clicking the small arrow in the panel header.
- Removing Menu Items:** Click the *Remove* link to delete the menu item. Click the *Cancel* link to cancel your changes to that menu item.


The menu items listed include: Home (Custom), About The Tests (Page), Clearing Floats (sub item), Page with comments (sub item), Navigation Label, Page with comments, Contributors (sub item), and Lorem Ipsum (Page). A 'Save Menu' button is located at the bottom right of the menu items list.

Adding a New Menu

Depending on the current Theme being used, your site may make use of more than one navigation menu. Sometimes you might have multiple menus in your site header, other times you may even have menus located in the sidebar or footer of your site.


To add a new menu, hover your cursor over the *Appearance* menu option in the left-hand navigation menu and in the fly-out menu, click the *Menus* link. Alternatively, click the *Appearance* menu option and then click the *Menus* link underneath.

On the screen that's displayed, click the *create a new menu* link. You'll be presented with a screen similar to below. Enter a name for your new menu in the *Menu Name* input field. Click the *Create Menu* button to create your new menu.



Editing an Existing Menu Item

Your current list of menu items resides in the right-hand column on the menu screen. If there are multiple menus on your site, there will be a dropdown list displayed at the top of the page that enables you to select the menu that you would like to edit. Simply select the menu you would like to edit from the *Select a menu to edit* dropdown list and then click the *Select* button. The menu items for your selected menu will then be displayed.



The items in this right-hand column on the *Menus* page will match the menu items that appear on your website. Clicking on the down arrow next to each menu item name will show an options panel for that particular menu item. In this options panel, there are several items that can be updated/changed. You can show or hide extra fields such as *Link Target*, *CSS Classes*, *Link Relationship (XFN)* or *Description* using the *Screen Options* tab at the very top-right of the screen.

- **URL** – Only displayed for Custom Links and will contain the URL to navigate to when that menu item is clicked
- **Navigation Label** – This is the label that will display within the actual menu on your website
- **Title Attribute** – This is the tooltip that appears when the mouse cursor hovers over the menu item

- **Open link in a new window/tab** – (Hidden by default) You can set the menu item to open in the same window or tab (which is the default) or in a new window or tab. This option is made visible by ticking the *Link Target* option on the *Screen Options* panel
- **CSS Classes** – (Hidden by default) Optional CSS Classes to add to this menu item. This option is made visible by ticking the *CSS Classes* option on the *Screen Options* panel
- **Link Relationship (XFN)** – (Hidden by default) Allows for the generation of XFN attributes so you can show how you are related to the authors/owners of site to which you are linking. This option is made visible by ticking the *Link Relationship (XFN)* option on the *Screen Options* panel
- **Description** – (Hidden by default) The description for the link. This may or may not appear, depending on the theme This option is made visible by ticking the *Description* option on the *Screen Options* panel

Each menu item can be moved to a new location in the menu hierarchy by using either the links underneath the *Navigation Label* input field or by clicking on the title area of the menu item and dragging ‘n dropping the menu to new location. If you choose to drag ‘n drop your menu items, the cursor will turn into a four-pointed arrow when you’re hovering over the correct area.


After making updates to your menu items, click the *Save Menu* button at the top or bottom of the screen.

Adding a New Menu Item

By default, only the Pages, Links and Categories panels are shown. If you’d like to add Posts, Tags or Post Formats as menu items, you simply use the *Screen Options* tab at the top-right of the screen to enable these panels as well.

To add a new Page as a menu item, tick the checkboxes in the *Pages* panel, next to each of the Pages that you’d like to add. You can select one Page at a time or multiple. After selecting your Pages, click the *Add to Menu* button. The new menu items will append to the bottom of the current list of menu items. The menu item name will default to the Page name. To change this, simply click on the down arrow next to the menu item name to view the options panel and then update the


Navigation Label to your preferred name. After making your updates, click the *Save Menu* button at the top or bottom of the screen. The steps to add a Post, Post Format, Category or Tag as a menu item are exactly the same as adding a Page.



To change the order that the menu options appear in, simply place your cursor over the title area of the menu item you'd like to move. When the cursor changes to a four-pointed arrow, click and drag the menu item to its new location. Depending on how your menu is configured within your theme, it's even possible to create the multi-level hierarchy required for dropdown menus. After moving your menu items around, don't forget to click the *Save Menu* button at the top or bottom of the screen to save your changes.

Adding a Custom Link Menu Item

Use the *Links* panel to add a custom link to your menu, such as a link to an external website. Simply type in the website URL in the *URL* field and the menu name in the *Link Text* field. Click the *Add to Menu* button when done. Use the same steps outlined previously to adjust the order of the menu item and click the *Save Menu* button at the top or bottom of the screen to save your changes.



Deleting a Menu Item

To delete a menu item click on the down arrow next to the menu item name to view the options panel for that item and then click the *Remove* link. After making your updates, click the *Save Menu* button at the top or bottom of the screen.


Managing Menu Locations

After you create a menu, you also need to tell WordPress where to use it. This is where the *Manage Locations* tab on the *Menus* page comes in.

After clicking the *Manage Locations* tab on the *Menus* page, you will be shown a page similar to below, with a list of the various menu locations used in your Theme. You may have one menu location or you may have multiple, depending on the Theme currently in use. Your menu location won't necessarily be called 'Top primary menu' either, as shown below. Again, that will depend entirely on your Theme.


Assign an existing menu that you've created to the appropriate location by selecting it from the dropdown list. Click the *Save Changes* button to save your changes.

Alternatively, you can choose to create a new menu and automatically assign it to the location by clicking the *Use new menu* link.




Header

The *Header* menu option will only be available if your current Theme is making use of this option. It allows you to choose an image to display in the header area. You can choose one of the images that comes with the theme or you can upload your own image. You can also choose to display a static image or a random image. The Site Title and Tagline in the header area can be turned on or off using the *Show header text with your image* option on this page. Again, depending on the theme you're using you may or may not have this, or a similar option.



Background

The *Background* menu option is another theme specific menu. It allows you to choose a background image and the background colour for the theme. Again, depending on the theme you're currently using you may or may not have this, or a similar option.



Editor

The Editor menu allows you to edit the individual [CSS](#) and [PHP](#) files which make up your Theme. Normally once a theme is installed and configured on your site, there's no need to make any changes within here. Extreme care should be taken with this option to avoid making changes to files that will affect how your site is displayed. Incorrectly modifying any files within this section can cause your site to display incorrectly or at worst, not at all. Extra caution must be taken if you intend to make any changes here.



It cannot be stressed enough how dangerous this option is if you know nothing about HTML, CSS or PHP. Modifying your theme files can drastically change how your site displays and depending on what gets changed, can even stop your site from displaying altogether.

Plugins


Plugins extend and expand the functionality of WordPress. Once a plugin is installed, you may activate it or deactivate it here. There are thousands of plugins available that provide a huge range of functionality. The easiest place to find them is within the official WordPress [Plugin Directory](#). You can search and install new plugins by clicking on the *Add New* button at the top of the page or the *Add New* link in the left-hand navigation menu.

Once a plugin has been added to your site, it needs to be ‘turned on’. To do this, click the *Activate* link to activate it. Depending on the plugin, you might also find that there are settings that need to be configured.

Activated plugins will be displayed with a different coloured background within your list of plugins. They will also be highlighted with a blue vertical bar down the left side of the row. If an activated plugin also has an updated version available, the background colour will change and the vertical bar will be red.

If any of your installed plugins have available updates, a small number will appear next to the *Plugins* menu option. The number will advise you as to how many plugins have updates available. A message will also be displayed just below the plugin name and description, advising that it has an update. Prior to updating a plugin, it’s wise to verify that the plugin functionality hasn’t changed significantly as to adversely affect your site. It’s also recommended to check that the plugin and your site still works as expected, once it has been updated.

If you have plugins that have been deactivated because you’re no longer using them, it’s good practice to remove them from your site. You can do this by clicking the *Delete* link underneath the plugin name.




Adding a New Plugin


To add a new plugin, click on the *Add New* link in the left-hand navigation menu or the *Add New* button at the top of the page.

The *Add Plugins* page will display a list of the current featured plugins from the WordPress.org Plugin Directory. You can use the links at the top of the page to filter the results to see Featured plugins, Popular plugins, Recommended plugins or a list of the plugins that you've marked as 'Favorite' within the WordPress.org Plugin Directory. If you click the *Favorites* link, you'll need to enter in your WordPress.org username and then click the *Get Favorites* button so that it can retrieve your list.

You can also click the *Search Plugins* input field and enter text to search for a specific plugin.




To view more information about a particular plugin, click the thumbnail image, the plugin name or the *More Details* link. A pop-up window will display more information about the plugin such as the plugin *Version*, *Author* and the date it was *Last Updated*. You can also read the full plugin description, installation notes, view screenshots and read any reviews that have been left.



After clicking the *Install Now* button, the plugin will be automatically downloaded to your site and installed. You are then given the option to activate the plugin or return to the plugin installer page.

On the *Add Plugins* page, you also have the option to manually upload a plugin to your site. To upload a plugin, click the *Upload Plugin* button at the top of the page.




Select your plugin file from your computer by clicking the *Browse...* button. Your plugin file must be uploaded in .zip format.

After clicking the *Install Now* button, your plugin will be automatically uploaded to your site and installed. You are then given the option to activate the plugin or return to the plugins page.

Users

This screen lists all the existing users for your site. Users with roles other than Administrator will see fewer options when they are logged in. Depending on your Role, you can also add new users as well as manage their Roles.

At the top of the screen there are links that allow you to filter the list of Users based on the User Roles. The number in brackets will advise how many there are for that particular type.



When hovering your cursor over each row in the list of Users, links will appear beneath the user name.

- **Edit** – Allows you to edit the user profile
- **Delete** – Allows the User to be deleted. This link won't be available for your own profile

A User can have one of five defined roles as set by the site admin: Site Administrator, Editor, Author, Contributor, or Subscriber.

- **Super Admin** – (Only relevant when running multiple sites from one WordPress installation). Someone with access to the blog network administration features controlling the entire network


- **Administrator** – Somebody who has access to all the administration features
- **Editor** – Somebody who can publish and manage posts and pages as well as manage other users' posts, etc.
- **Author** – Somebody who can publish and manage their own posts
- **Contributor** – Somebody who can write and manage their posts but not publish them
- **Subscriber** – Somebody who can only manage their profile

When WordPress is first installed, an Administrator account with all capabilities is automatically created.

The [avatar](#) that is displayed in the list of Users is using what's called a Gravatar. A Gravatar is a Globally Recognized Avatar. Gravatars are currently used by a huge number of blogs, forums, chat sites and the like. Rather than having to upload an avatar on each and every system you sign up to, Gravatars allow you to have one avatar that is viewable everywhere. To create a Gravatar, simply go to [gravatar.com](#) and sign up. To use your Gravatar within WordPress, simply add an email address to your Profile that you've configured within the Gravatar site and it will automatically display.

Adding a New User

To add a new user, click on the *Add New* link in the left-hand navigation menu or the *Add New* button at the top of the page.




Once the above page is displayed, simply fill in the various fields and click the *Add New User* button.

- **Username** – (mandatory) Enter the username of the new user here. This will also be used as the Login name for the user. Once saved, the Username can't be changed
- **E-mail** – (mandatory) Enter a valid email address of the new user here. The email address must be unique for each user. If a published Post or Page is authored by this user and approved comments are made to that post or page, a notification email is sent to this email address
- **First Name** - Enter the first name of the new user here
- **Last Name** – Enter the last name of the new user in this text box
- **Website** – You may enter the new user's website URL in this text box

- **Password** – (mandatory) Enter a password for the new user
- Repeat **Password** – (mandatory) Enter your password a second time to confirm it
- **Strength indicator** – This indicates if the password you entered is Very Weak, Weak, Medium, or Strong (displayed in green). The stronger the password the more secure the login. *Hint:* The password should be at least seven characters long. To make it stronger, use upper and lower case letters, numbers and symbols like ! " ? \$ % ^ &)
- **Send Password?** – Check the box to send this password to the new user by email
- **Role** – Select the desired Role for this user from the dropdown list

Deleting a User

To delete a user, click on the *Delete* link that appears beneath the user name when hovering your cursor over each row. The *Delete* link won't appear for the user that is currently logged in.



Along with deleting the user you will be given the choice of what to do with all the content currently assigned to that User. The available choices are:

- **Delete all content** – This will delete all the content which this user created

- **Attribute all content to** – This will assign all the content currently linked to this User, to another User of your choosing. Simply select the User from the dropdown list

After making your selection, click the *Confirm Deletion* button to remove the User.

Editing your Profile

To edit your profile details, simply click on your user name, when viewing the list of Users or click on the *Edit* link that appears beneath your user name when hovering your cursor over each row. Alternatively, click on the *Your Profile* link in the left-hand navigation.

WordPress Dashboard: Your WordPress Site | 0 | + New | Howdy, Joe Blogg | Help

Edit your Profile

Update the various fields for your profile. The *Username* field can't be changed.

Profile

Personal Options

Visual Editor Disable the visual editor when writing

Admin Color Scheme

- Default
- Light
- Blue
- Coffee
- Ectoplasm
- Midnight
- Ocean
- Sunrise

Keyboard Shortcuts Enable keyboard shortcuts for comment moderation. [More information](#)

Toolbar Show Toolbar when viewing site

Name

Username Names cannot be changed.

First Name

Last Name

Nickname (required)

Display name publicly as

Contact Info

E-mail (required)

Website **Edit your Profile**
The *Biographical Info* may or may not be displayed when creating Posts. It depends entirely on the Theme that is currently in use.

About Yourself

Biographical Info

Share a little biographical information to fill out your profile. This may be shown publicly.

New Password

If you would like to change the password type a new one. Otherwise leave this blank.

Repeat New Password

Type your new password again.

Strength indicator Hint: The password should be at least seven characters long. To make it stronger, use upper and lower case letters, numbers, and symbols like ! * ? % ^ &).

Log Out of All Other Sessions

Left your account logged in at a public computer? Lost your phone? This will log you out everywhere except your current browser.

Save Updated Profile

After updating your profile, click the *Update Profile* button to save your changes.

Thank you for creating... Version 4.1

If you're an Administrator and would like to edit someone else's profile, click on their user name when viewing the list of Users or click on the *Edit* link that appears beneath their user name when hovering your cursor over each row.

Update the appropriate fields and then click the *Update Profile* button to save all your changes.

Personal Options

- **Visual Editor** – Checking this box disables the Visual Editor when writing and uses the plain html editor
- **Admin Color Scheme** – Check this radio button next to the colour scheme desired for the administrative panels. You have the choice of eight different color schemes
- **Keyboard Shortcuts** – Checking this box Enables keyboard shortcuts for comment moderation. Keyboard shortcuts are designed to allow you to rapidly navigate and perform actions on comments
- **Toolbar** – Checking this box will display the Admin Bar at the very top of your website (only for the person who is currently logged in)

Name

- **Username** – You cannot edit your Username because it is used as your Username during the login process. Even an Administrator cannot change your Username. Usually, no one else ever needs to see your Username
- **First name** – Enter your first name in this text box
- **Last name** – Enter your last name in this text box
- **Nickname** – (mandatory) The nickname is a requirement for every user. It may be the same as your Username or it can be different. If you don't supply a Nickname, then the Username will be placed in this field
- **Display name publicly as** – Select how your name is cited on your blog, from the dropdown list. You can choose from several choices: Nickname, Username, First Name, Last Name, 'First Last', or 'Last First'. If you prefer 'Last First', insert a comma after your last name in the *Last Name* text field

and choose the last option from the dropdown list. For security reasons, it's a good idea to keep this different from your Username

Contact Info

- **E-mail** – (mandatory) All users are required to list an email address in their respective Profiles. The email address must be unique for each user. Your blog will use this address to notify you of new comments to your posts and for other administrative purposes. Only other registered users of your blog will have access to this email address. It is never sent anywhere
- **Website** – Enter your website address

About Yourself

- **Biographical Info** – Enter a short description or profile of yourself here. Depending on your theme, this optional information may be displayed when creating new Posts
- **New Password** – Enter your new password. Leaving this input field and the *Repeat New Password* field blank will keep the password you are currently using
- **Repeat New Password** – Enter your password a second time to confirm it
- **Strength Indicator** – This indicates if the password you entered is Very Weak, Weak, Medium, or Strong (displayed in green). The stronger the password the more secure your login. *Hint:* The password should be at least seven characters long. To make it stronger, use upper and lower case letters, numbers and symbols like ! " ? \$ % ^ &)

If you've left your account logged in at a public computer or you've lost your phone, you can click the *Log Out of All Other Sessions* button to log you out of everywhere except for your current browser.

Tools

The *Tools* menu provides some handy administration tools. Most of the time though, they're used when setting up or configuring your WordPress site and so as such, they won't be covered here in great detail.

Press This

Press This is a bookmarklet: a little app that runs in your browser that lets you grab bits of the web. It provides you with a handy shortcut within your browser to creating new Posts. Simply Drag-and-drop the *Press This* link to your bookmarks bar or right click it and add it to your browser favourites for a posting shortcut.

Categories and Tags Converter

The *Categories and Tags Converter* is a tool to convert existing Categories to Tags or Tags to Categories. Before it can be used it must be installed via the *Import* menu option.

Import

The *Import* option provides you with various tools for importing content from other blogging systems. You can import content from Blogger, LiveJournal, Moveable Type, TypePad and Tumblr. You can also import content from Blogrolls that use the [OPML Format](#), posts from an RSS feed or content from other WordPress sites. To import content from another WordPress site you first need to install the [WordPress Importer](#) plugin. To import content from another type of site other than WordPress, you'll be prompted to install the relevant Importer plugin after selecting the type of site that you'd like to import your content from.

Export

The *Export* option is used to export your data in XML format, from your WordPress site. The export format is called *WordPress eXtended RSS* or WXR and will contain your posts, pages, comments, custom fields, terms, navigation menus

and custom posts. Once you've saved the download file, you can use the *Import* function on another WordPress site to import the content from this site.

Settings

The various *Settings* screens are used to configure your WordPress site. Normally, once your WordPress site is set up there's no reason to change any of these settings. These *Settings* options will only be touched upon very briefly. You can find out lots more information in regards to configuring your site within the [WordPress Codex](#).

General

The *General* settings configure your basic site preferences such as the Site Title and Tag Line, the WordPress Address and Site Address, the administrators email address and the date and time format, among other things.

The *WordPress Address (URL)* is the location of your main WordPress core files. The *Site Address (URL)* is the address you want to use for your site homepage. Usually these two URL's are the same but they can be different if, for example, you have your WordPress files stored in a subdirectory.

When you install WordPress, you get the option to select the language that you'd like to use within the Dashboard. After installation, if you'd like to change the language, you can select this using the *Site Language* dropdown at the bottom of the page.

The screenshot shows the WordPress dashboard's 'General Settings' page. The left sidebar contains navigation links: Dashboard, Posts, Media, Pages, Comments, Appearance, Plugins, Users, Tools, Settings (highlighted), General, Writing, Reading, Discussion, Media, and Permalinks. The main content area is titled 'General Settings' and includes the following fields:

- Site Title:** Your WordPress Site
- Tagline:** Just another WordPress site. Subtext: *In a few words, explain what this site is about.*
- WordPress Address (URL):** http://your-wordpress-site.com
- Site Address (URL):** http://your-wordpress-site.com. Subtext: *Enter the address here if you want your site homepage to be different from the directory you installed WordPress.*
- E-mail Address:** joe@your-wordpress-site.co. Subtext: *This address is used for admin*
- Membership:** Anyone can register
- New User Default Role:** Subscriber
- Timezone:** Melbourne. UTC time is 2014-12-21 8:54:44. Local time is 2014-12-21 19:54:44. Subtext: *Choose a city in the same timezone as you.* Below this, it states: *This timezone is currently in daylight saving time. Standard time begins on: April 5, 2015 3:00 am.*
- Date Format:** December 21, 2014. Other options: 2014-12-21, 12/21/2014, 21/12/2014, Custom: F j, Y December 21, 2014
- Time Format:** 7:54 pm. Other options: 7:54 PM, 19:54, Custom: g:i a 7:54 pm. Subtext: [Documentation on date and time formatting.](#)
- Week Starts On:** Monday
- Site Language:** English (United States)

Three callout boxes are present:


- Top callout: **General Settings**. Configure your Site Title, Tagline, WordPress Address (URL) and Site Address (URL).
- Middle callout: **General Settings**. Select the correct Timezone for your site along with the Date Format and Time Format.
- Bottom callout: **General Settings**. Select the correct Site Language for your site. This will change the language that is displayed in the Dashboard.

A 'Save Changes' button is located at the bottom left of the settings area.

Writing

The *Writing* settings configure various options with regards to your site content. Settings include defining the *Default Post Category*, *Default Post Format* (if

supported by your Theme) and if the Link Manager plugin is installed, the *Default Link Category*.




Reading

The *Reading* settings configure how your site is viewed. You can define whether your front page displays a static Page or your blog Posts, how many blog posts are displayed by default as well as Syndication/RSS options. If you configure your site

to display a static front page, you can set which page to display and also which page will show your blog posts.

The *Search Engine Visibility* setting enables you to block your site from search engines or allow it to be visible.



Discussion

The *Discussion* settings define how your readers interact with your site and how your site interacts with other blogs. You can configure [Pingbacks](#) and [Trackbacks](#), whether readers can post Comments or not and if so, how those Comments are moderated and displayed on your site.

This screen also lets you configure whether the Post Author should be emailed whenever someone posts a comment on your site. If you are receiving emails whenever someone posts a comment, simply uncheck the box next to *Anyone posts a comment* within the *E-mail me whenever* section on this screen and then save your changes.

If you would like to be notified whenever a comment is held for moderation, it can be configured on this screen as well within the *E-mail me whenever* section. The email notification is sent to the email address listed on the *Settings > General* page.

WordPress Dashboard: Your WordPress Site | Howdy, Joe Blog

Discussion Settings

Default article settings

- Attempt to notify any blogs linked to from the article
- Allow link notifications from other blogs (pingbacks and trackbacks)
- Allow people to post comments on new articles

(These settings may be overridden for individual articles.)

Other comment settings

- Comment author must fill out name and e-mail
- Users must be registered and logged in to comment
- Automatically close comments on articles older than 14 days
- Enable threaded (nested) comments: 5 levels deep
- Break comments into pages with 50 top level comments per page

last page displayed by default

Comments should be displayed with the older comments at the top of each page

E-mail me whenever

- Anyone posts a comment
- A comment is held for moderation

Before a comment appears

- Comment must be manually approved
- Comment author must have a previously approved comment

Comment Moderation

Hold a comment in the queue if it contains 2 or more links. (A common characteristic of comment spam is a large number of hyperlinks.)

When a comment contains any of these words in its content, name, URL, e-mail, or IP, it will be held in the [moderation queue](#). One word or IP per line. It will match inside words, so "press" will match "WordPress".

Comment Blacklist

When a comment contains any of these words in its content, name, URL, e-mail, or IP, it will be marked as spam. One word or IP per line. It will match inside words, so "press" will match "WordPress".

Avatars

An avatar is an image that follows you from weblog to weblog appearing beside your name when you comment on avatar enabled sites. Here you can enable the display of avatars for people who comment on your site.

Avatar Display

- Show Avatars

Maximum Rating

- G — Suitable for all audiences
- PG — Possibly offensive, usually for audiences 13 and above
- R — Intended for adult audiences above 17
- X — Even more mature than above

Default Avatar

For users without a custom avatar of their own, you can either display a generic logo or a generated one based on their e-mail address.


- Mystery Person
- Blank
- Gravatar Logo
- Identicon (Generated)
- Wavatar (Generated)
- MonsterID (Generated)
- Retro (Generated)

Save Changes

Media

The *Media* settings define the default image sizes that are created when an image is uploaded.

You can also configure whether your uploaded media files are stored in folders based on the year and the month of the upload.



Permalinks

The *Permalink* settings enable you to configure the URL format that is displayed in the web browser when someone browses your site. By default WordPress uses web URLs which have question marks and lots of numbers in them however you can change this so that the URL is more user friendly. This also helps considerably with Search Engine Optimisation (SEO). To change the way your site URL is displayed simply select one of the radio button options within the *Common Settings* section on this screen. Next to each option is an example of how the URL would be displayed.

WordPress Dashboard: Your WordPress Site | 0 | + New | Howdy, Joe Blogg | Help

Permalink Settings

By default WordPress uses web URLs which have a standard structure for your permalinks and archives. This structure is called the "Default" structure. However, WordPress offers you the ability to create a custom URL structure for your permalinks and archives. A [number of tags are available](#), and here are some examples to get you started.

Common Settings

- Default: `http://your-wordpress-site.com/?p=123`
- Day and name: `http://your-wordpress-site.com/2014/12/20/sample-post/`
- Month and name: `http://your-wordpress-site.com/2014/12/sample-post/`
- Numeric: `http://your-wordpress-site.com/archives/123`
- Post name: `http://your-wordpress-site.com/sample-post/`
- Custom Structure: `http://your-wordpress-site.com /%postname%/`

Optional

If you like, you may enter custom structures for your category and tag URLs here. For example, using "topics" as your category base would make your category links like `http://your-wordpress-site.com/topics/uncategorized/`. If you leave these blank the defaults will be used.

Category base:

Tag base:

[Save Changes](#)

Permalink Settings
WordPress allows you to configure a custom URL structure for your pages.

Keeping your Site Updated

From time to time, themes, plugins & WordPress will require updating. Updates typically happen when developers release security patches or add extra functionality.

It's good practice to keep your themes, plugins & WordPress version updated to the latest versions. The top two reasons for sites being hacked are insecure passwords & outdated (vulnerable) software.

WordPress has introduced automatic background updates in an effort to promote better security and to streamline the update experience. By default, only minor WordPress releases are enabled (e.g. v3.9.1, v4.1). These minor releases are usually for maintenance and security purposes or translation file updates. Only core WordPress files will be auto-updated. Your themes or plugins won't be automatically updated.

Once your site is auto-updated your site administrator will be notified by email. If your WordPress installation can't update itself automatically for one reason or another, your site administrator will be notified of this as well.

To update your WordPress version manually or to update your themes and plugins, hover your cursor over the *Dashboard* menu option in the left-hand navigation menu and in the fly-out menu, click the *Updates* link. Alternatively, click the *Dashboard* menu option and then click the *Updates* link underneath.

The *Updates* page is divided into three sections. If your version of WordPress requires updating, this will be displayed at the top of the page. Below that, you'll be notified of any plugin updates and below that again, theme updates.

Updating your WordPress version is as simple as clicking the blue *Update Now* button. WordPress will download the necessary files, perform a validation of those files and then automatically update your site.

Before updating your site, it's always wise to perform a backup first, just in case something unfortunate happens during or after the installation.

The screenshot shows the WordPress dashboard's 'Updates' section. At the top, it says 'WordPress Updates' and 'Last checked on December 20, 2014 at 3:41 pm.' with a 'Check Again' button. A warning message states: 'Important: before updating, please back up your database and files. For help with updates, visit the Updating WordPress Codex page.'

WordPress Updates: An updated version of WordPress is available. You can update to [WordPress 4.1](#) automatically or download the package and install it. There are 'Update Now' and 'Download 4.1' buttons. A callout box titled 'Updating WordPress' says: 'You will be notified if your WordPress version is out of date. Click the *Update Now* button to update your WordPress files.'

Plugins: The following plugins have new versions available. Check the ones you want to update and then click "Update Plugins". There is an 'Update Plugins' button. A list of plugins is shown with checkboxes:

- Select All
- Akismet: You have version 3.0.1 installed. Update to 3.0.4. [View version 3.0.4 details.](#) Compatibility with WordPress 4.1: 100% (according to its author)
- Select All

A callout box titled 'Updating Plugins' says: 'Select the plugins you wish to update and click the *Update Plugins* button.'

Themes: The following themes have new versions available. Check the ones you want to update and then click "Update Themes". Please Note: Any customizations you have made to theme files will be lost. Please consider using [child themes](#) for modifications. There is an 'Update Themes' button. A list of themes is shown with checkboxes:

- Select All
- Twenty Fourteen: You have version 1.1 installed. Update to 1.3.
- Twenty Thirteen: You have version 1.2 installed. Update to 1.4.
- Select All

A callout box titled 'Updating Themes' says: 'Select the themes you wish to update and click the *Update Themes* button.'

If there are any plugins that can be updated, these will be listed in the *Plugins* section on the page. To update your plugins, tick the boxes next to each of the plugins you wish to update and then click the *Update Plugins* button. The new plugin files will be downloaded and automatically installed.

If there are any themes that can be updated, these will be listed in the *Themes* section on the page. To update your themes, tick the boxes next to each of the themes you wish to update and then click the *Update Themes* button. The new theme files will be downloaded and automatically installed.

After your site has been updated, no matter whether it's been done automatically, manually or just themes and plugins, it's a good idea to give your site a quick test to make sure it's functioning as expected. This will ensure that the new themes, plugins or even WordPress itself hasn't introduced new functionality that adversely affects your site or changes how your site operates.

Where To From Here?

If you're looking for more resources to further your WordPress knowledge the first place to check out is the WordPress.org website. There you'll find technical support and new resources like plugins which are a fantastic way to add extra functionality to your site without having to modify your theme files. The [Plugin Directory](#) has over 35,000 different plugins that are available to download, for free. Furthermore, if you want to change how your site looks, have a look in the WordPress [Themes Directory](#) which is also there on the WordPress site.

If you find you need more information on a particular topic, have a search through the [WordPress Codex](#) which goes into greater detail about how WordPress works. Not only will you find information about updating your site content but there is all sorts of other useful information that will help you with installing WordPress, troubleshooting, using plugins & themes and also theme development, for the more technically minded.

Once your website is humming along nicely, you might want to think about getting involved in the awesome WordPress community. One of the easiest ways to get involved is simply by helping others within the [WordPress Support Forums](#). There is always someone there who's newer to the learning curve than you, and learning is so much improved while you're teaching others! There are topics there for all ability levels, from installation issues, theme and template issues, and general troubleshooting all the way through to more advanced areas of theme and plugin development.

It's a great benefit not just for yourself, but for others as well in getting more involved in the WordPress community. This could be through core commits, UI design, testing beta releases or even just helping people on the WordPress forums. Or, how about getting along to Meetups where users and developers alike get together and learn from and teach each other, show off the projects they're working on and meet others to collaborate with. The more we work together to make WordPress great, the more robust the platform becomes. Everyone wins!

Last but not least, don't forget to keep in touch with us on the web;

<http://easywpguide.com>